SCO UnixWare 7.1.4 (UW714) 安裝說明

SCO UnixWare 7.1.4系統硬體安裝需求:

硬體	最低安裝要求	建議規格	最高支援
處理器	IntelR Celeron(R), Pentium(R), Pentium II, Pentium III, Pentium III Xeon, Pentium 4, or Intel Xeon或其他相容處理器, 例如, AMD Athlon(TM), Athlon 64, Duron(TM), Sempron(TM), 或 Opteron(TM)(32-bit mode)	Pentium P4	32 CPUs
記憶體	32MB, 128MB(視窗環境)	256MB	64GB
磁碟空間	約 2GB	8GB	1TB(per disk)
HBA	IDE	SCSI, SATA	1024

SCO UnixWare 7.1.4版本:

Edition	Small Business	Base	Business	Departmental	Enterprise	Data Center
使用者 數	1	1	10	25	50	150
記憶體	1GB	2GB	4GB	8GB	16GB	32GB
處理器	1	1	4	4	6	8

以下我們將針對SCO UnixWare 7.1.4 (UW714)的安裝步驟一一說明, 同時搭配實際安裝畫面以提供解釋。

安裝步驟

1. 放入UnixWare 7.1.4光碟片,以CD-ROM開機方式啟動系統,系統 自動會進入第一個語言選擇畫面,由於UnixWare 7.1.4並不提供繁體 中文版本,因此,請直接選擇英文版進入.



2. 系統顯示系統安裝說明與按鍵的設定,請直接按F10鍵



3. 顯示Locale地區選擇,請直接接受預設值,按F10鍵繼續 UnixWare 7, Release 7.1.4 Installation

<pre>(±) Americas (Latin-1) () Eastern Europe (Latin-5) () Central Europe (Latin-2) () Western Europe (Latin-1) () Northeast Asia () Other () All Locales</pre>		Choose a	ι zone for	this syste	M and pres	ss <f10></f10>	
			(<u>*</u>) Amer () East () Cent () West () Nort () Othe () All	icas (Latin ern Europe ral Europe ern Europe heast Asia r Locales	-1) (Latin-5) (Latin-2) (Latin-1)		
Selected zone: Americas (Latin-1)	Selected zone:	Americas	(Latin-1)	ZE10N-Novt	0 mm cr +	koup or	(Tab)-Sel

4. 同上,請接受預設值C (English),按F10鍵繼續

http://tw.sco.com/tech/uw714install.htm

Uni×Ware 7,	Release 7.1.4 Installation
Choose a locale	for this system and press <f10>.</f10>
(<u>≭</u>) C (English)	() Spanish for Chile
() POSIX (English)	() Spanish for Mexico
() English for Canada	() Spanish for Venezuela
() English for USA	() French for Canada
() Spanish for Hrgentina	() Portuguese for Brazil
leated leaster C (Partick)	
(F1)=Heln (F9)=Back	(F10)=Next Arrow keys or (Tab)=S

5. 設定鍵盤選擇,請直接選擇United States



6. 輸入系統使用序號,若無系統使用序號,可以F8鍵使用60天測試

序號						
	Un i xWa	re 7, Rele	ase 7.1.4 In	stallat	ion	
	l f	Syst	ем License -		1	
	Licen	se Number				
	Licen	ahol as	_			
	LICEN	se coue				
	Licen	se Data				
	L					
	ana - 🕶 Katabababa		TOX 4	- 1220		
<pre>Kinter your Syst</pre>	em License, <f8≻=defer< td=""><td><pre>or press < <f9>=Back</f9></pre></td><td><pre><f10> cont1 <f10>=Next</f10></f10></pre></td><td>Arrow</td><td>keys or</td><td><tab>=Se</tab></td></f8≻=defer<>	<pre>or press < <f9>=Back</f9></pre>	<pre><f10> cont1 <f10>=Next</f10></f10></pre>	Arrow	keys or	<tab>=Se</tab>

7. 詢問是否有額外的HBA驅動程式需要載入,若有(例如AHCI),則請 放入HBA磁片後,選擇 Install HBA drivers,否則請直接選擇 Proceed with installation

 UnixWare 7, Release 7.1.4 Installation

 If you have Host Bus Adapter (HBA) drivers on diskette, CD-ROM, or removable USB storage Media, select "Install HBA drivers", insert the Media and press <F10> to continue.

 If you do not have HBA Media to install, select "Proceed with installation" and press <F10> to continue.

 Choose One

 () Install HBA drivers

 (*) Proceed with installation

 (*) Proceed with installation

 (*) Proceed with installation

8. 詢問是否須進入DCU檢查硬體配置,請選擇預設值, Do not enter the DCU並繼續



9. 設定主機名稱(請勿包括網域名稱)

	3	UnixWare 7, I	Release 7.1.4	4 Installation	
		Si	ustem Node Na	ame	
Name:	uw714_				
			A DE LA PARTA DE LA DATA DE DE LA		
Enter the n <f1>=He</f1>	ode name f lp	or your syste	And press <f9>=Back</f9>	<f10>.</f10>	<f10>=N</f10>

10. 選擇安裝方式, 一般而言, 均為CD-ROM安裝

	UnixWare 7	, Release 7.1.4 I	Installat	ion	
		nstallation Metho	od		
	Install Install	from CD-ROM from TCP network	server		
	Cancel i	nstallation and s	shut down	(
Install from CD-RO	DM.				
<f1>=Help</f1>	<f9>=Back</f9>	<f10>=Next</f10>	Arrow	keys or	<tab>=Se</tab>

11. 設定硬碟,可以直接接受預設值,選擇Use whole disk for



12. 若選擇Customize partitions,則會看到此畫面,請設定好正確的磁區規劃,請注意 SCO建議若無其他作業系統,則請設定100%的磁區為UNIX,並設定為Active



13. 設定檔案系統file system規劃,若無其他需求,可以直接選擇預設值



14. 詢問是否進入更細部的硬碟硬體偵測,請直接選擇預設值



15. 詢問所需安裝的軟體套件,若無其他需求,一般而言,請選擇預設值

Choose this p you entered o installed, an Current Licen	profile to select packages based on t earlier. The correct software is auto nd licensed. nse: "Business Edition"	he type o Matically	of licens selecte
	Choose System Profile	430 11	MR
	License-Based Defaults	430.11 150.92	MB
	License-Based Defaults Small Footprint Server Full (All Packages)	430.11 150.92 436.27	MB MB MB
	<mark>License-Based Defaults</mark> Small Footprint Server Full (All Packages) Customize Installation of Packages	430.11 150.92 436.27 430.11	MB MB MB MB

16. 設定網路卡,若無其他需求(比如說有第二張,或第三張網路卡) 則請直接選擇預設值,若沒有出現此畫面,則代表目前系統無法偵測 網路卡,可於作業系統安裝完畢後,再重新安裝網路卡驅動程式,屆 時可利用scoadmin管理工具(或直接netcfg命令)安裝 UnixWare 7, Release 7.1.4 Installation The following network interface adapter(s) were detected: Bus BusNum Slot Network Adapter Name PCI 0 3 AMD PCnet family mdi driver Select Network Adapter $(\underline{*})$ Use the detected adapter shown above. () Select from the full list of supported adapters. () Defer network configuration. <F1>=Help <F9>=Back <F10>=Next Arrow keys or <Tab>=Se

17. 設定TCP/IP設定, 可參考本範例設定

Use DHCP?	no
System IP Address System Netmask Broadcast Address Default Router Domain Name Primary DNS Address Other DNS Address Other DNS Address	192.168.1.37 255.255.255.0 192.168.1.255 192.168.1.1 sco.com.tw 168.95.1.1_
Domain Name DNS Address DNS Address DNS Address DNS Address	sco.com.tw 168.95.1.1 <u>_</u>
Frame Format	ETHERNET II

18. 設定滑鼠,請選擇預設值

A PS2 Mouse has been detected on device node /dev/m320. (*) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration	A PS2 Mouse has been detected on device node /dev/m320. (*) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration		UnixWare 7, Release 7.1.4 Installation
(≝) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration	(*) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration	A	PS2 Mouse has been detected on device node /dev/m320.
(≝) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration	(≝) Configure∕Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration		
(≛) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration	(≚) Configure∕Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration		
 (*) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration 	(<u>*</u>) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration		
			 (★) Configure/Re-configure this Mouse () Manually configure a mouse () Defer mouse configuration

19. 自動偵測滑鼠,若正確,請按F10繼續

Un i xWar	re 7, Release 7.	1.4 Installation	
Please select t number of butto	the number that ons on your PS/2	correctly describ -compatible mouse	es the
	PS/2 Mou Number of but	se tons 2	
<f2>=Choices</f2>	<f10>=Next</f10>	Arrow Keys or <	Tab>=Move

20. 系統會提示測試滑鼠,請按F10,並作滑鼠測試



21. 設定時區與時間,請修改Timezone,依照實際狀況選擇

http://tw.sco.com/tech/uw714install.htm

	UnixWare 7, Release 7.1.	4 Installation
Year: Month: Date: Hour: Minute: Timezone:	Date and Tim 2006 4 26 10 51 Taiwan	le
<f1>=Help</f1>	<₽2>=Timezone Choices	<f9>=Back <f10>=N</f10></f9>

22. 選取安全性規則,若無其他需求,可以直接接受預設值 Traditional

	UnixWare	7, Release 7.1.4	Installa	tion	
	Choose	the desired secur	ity leve	1.	
		<mark>Choose One</mark> Low <mark>fraditional</mark> Iмproved (C2) High (Above C2)			
<f1>=Help</f1>	<f9>=Back</f9>	<f10>=Next</f10>	Arrow 1	keys or	<tab>=Sel</tab>

23. 設定系統擁有者(System Owner)密碼

System оwn	er name
System owner name:	owner
System owner login name:	owner
System owner user ID number:	101
System owner password:	****
Repeat password:	****

24. 設定系統管理者(root)密碼

	UnixWare 7, J	Release 7.1.4 Ins	tallation	
	_	loot Password		
	Root nassword	****		
	ROOT pussion ut			
	Repeat root pas	sword: ****_		
etupe the root	password and press	s <enter>.</enter>		
<f1>=Help</f1>	<f9>=Back</f9>	<f10>=Next</f10>	Arrow keys	; or <



26. 之後,系統會自動安裝第一片光碟片內容,以Pentium 4系統為例,此步驟約需40分鐘.

第一片光碟安裝完畢後,系統會自動重新開機,並且要求放入第二片 安裝光碟.請依照提示放入後,按F10



27. 列出第二片光碟內容後,請依照實際狀況選擇,一般而言,可以 直接接受預設值,並且按F10繼續安裝

Univilare 7 1 4 Undates CD-DOM Heluwe 2	
Unixware 7.1.4 Opuates CD-Ron Obtume 2	
Select products to Install	
(_) Linux Kernel Personality for UnixWare 7	799.53 M
() Linux Kernel Personality documentation	.23 M
(*) Java Communications API, V2.0	.72 M
(*) Java 2 SE, V1.4.2 Software Development Kit	21.62 M
(*) Java 2 SE, V1.4.2 Runtime Environment	49.83 M
(*) (URW)++ Free X11 Fonts	2.12 M
() Common Unix Printing System	2.72 M
() Common Unix Printing System Development Environment	.31 M
() Common Unix Printing System Documentation	3.21 M
() Gimp-Print Printer Drivers and PPDs	9.68 M
() ESP Ghostscript - PS/PDF Interpreter and Renderer	12.55 M
(Page Down for more)	
Free space: 2270.49 MB Selected: 74.44 MB Available: 2	196.05 MB
<pre><f1>=Help <f8>=Defer Arrow keys or <tab>=Move <space>=Sele</space></tab></f8></f1></pre>	ct <f10>=</f10>

第二片光碟安裝約需20分鐘,安裝完畢,系統會提示是否繼續安裝第 三片光碟,若無其他需求,請直接跳過第三片光碟的安裝,預設一般 商業用途的UnixWare 7.1.4作業系統可以不須安裝第三片光碟.最後 系統會提示重新啟動系統,重新啟動系統後,作業系統安裝工作則大 功告成.

28. 最後,請上 <u>http://www.sco.com/support/download.html</u> 或 <u>ftp.sco.com</u> 下載相關SCO UnixWare 7.1.4修正,例如Maintenance Pack。

本文所提及之公司名稱與產品商標分屬各公司或個人所有. 文件提供: SCO TAIWAN許景超<u>(kevinhsu@sco.com)</u>