



 Apple Computer, Inc.

© 1995 Apple Computer, Inc. All rights reserved.

Under the copyright laws, this manual may not be copied, in whole or in part, without the written consent of Apple. Your rights to the software are governed by the accompanying software license agreement.

The Apple logo is a trademark of Apple Computer, Inc., registered in the U.S. and other countries. Use of the “keyboard” Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws.

Every effort has been made to ensure that the information in this manual is accurate. Apple is not responsible for printing or clerical errors.

Apple Computer, Inc.
1 Infinite Loop
Cupertino, CA 95014-2084
(408) 996-1010

Apple, the Apple logo, AppleCD, AppleShare, HyperCard, LaserWriter, Macintosh, and Performa are trademarks of Apple Computer, Inc., registered in the U.S. and other countries.

AppleScript, At Ease, Balloon Help, Finder, Mouse Practice, PowerTalk, and QuickDraw are trademarks of Apple Computer, Inc.

Adobe, Adobe Illustrator, Adobe Photoshop, and PostScript are trademarks of Adobe Systems Incorporated, which may be registered in certain jurisdictions.

ClarisWorks is a trademark of Claris Corporation.

Earth Explorer is a trademark of Enteractive, Inc.

ExposurePro is a registered trademark of Baseline Publishing, Inc.

Helvetica and Times are registered trademarks of Linotype-Hell AG.

QuarkXPress is a registered trademark of Quark, Inc.

SuperPaint is a trademark of Aldus Corporation, a subsidiary of Adobe Systems Incorporated, which may be registered in certain jurisdictions.

Tektronix is a registered trademark of Tektronix, Inc.

Simultaneously published in the United States and Canada.

Mention of third-party products is for informational purposes only and constitutes neither an endorsement nor a recommendation. Apple assumes no responsibility with regard to the performance or use of these products.



Contents

.....

1 Welcome to At Ease 1

- What is At Ease? 1
- About this book 2
- What you need to know before you begin 3
- Other sources of information 3

2 Installing At Ease on Your Computer 5

- Restrictions on copying At Ease 5
- What do you need to run At Ease? 5
- Installing At Ease 6
- Installing Mouse Practice 8

3 Setting Up At Ease for Users 11

- Opening the At Ease Setup program 12
- Getting on-screen instructions for At Ease setup 13
 - On-screen instructions with system software version 7.0 or 7.1 13
 - On-screen instructions with system software version 7.5 or later 14
- Setting an administrator password 17
- Registering yourself as the At Ease owner 19

Registering other users	20
Registering an At Ease user	21
Registering a restricted Finder user	33
Registering a regular Finder user	42
Duplicating an existing user's privileges	45
Removing users	46
Making changes to a user's access privileges	46
Turning At Ease on	47
Quitting the At Ease Setup program	47
Where to go from here	47

4 Additional Features of At Ease Setup 49

Customizing access to CD-ROM discs	49
Giving all users access to an item at the same time	52
Revoking all users' access to an item at the same time	53
Giving users access to shared disks	54
Setting application preferences	56
Changing the user greeting	58
Adding and removing button sounds	59
Preparing to attach a sound	59
Importing a sound	60
Recording a sound	62
Removing a sound	63
Turning off At Ease	63
Removing At Ease permanently	64
If you have the <i>At Ease Install</i> disk	64
If you don't have the <i>At Ease Install</i> disk	65

5 Tips and Troubleshooting 67

- General tips 68
- Troubleshooting suggestions 68
- If you forget the administrator password 70
- Tips for using At Ease 3.0 with System 7.5 71




A Working in At Ease 75

- Starting up with At Ease 75
- A first look at At Ease 77
- Switching between At Ease panels 78
- “Paging” through At Ease panels 79
- Opening programs, documents, and folders 80
- At Ease menus 80
 - The Apple menu 80
 - The File menu 81
 - The Edit menu 90
 - The View menu (optional) 90
 - The Special menu 91
- Saving documents 93
- Changing your password 94
- Setting the number of colors for a program 95
- Getting help 96
 - Using Balloon Help 96
 - Using At Ease Guide 97
- Tips and shortcuts 101

B Working in the Restricted Finder 103

- Starting up with the restricted Finder 103
- Differences between the regular Finder and the restricted Finder 106

Index 107



1

Welcome to At Ease



This chapter introduces At Ease 3.0. You can save time later if you take a few minutes now to learn about At Ease and how you use it.

What is At Ease?

At Ease allows you to customize your computer for each person who uses it. By providing a choice of working environments, At Ease lets you tailor the computer's interface for users of all ages and experience levels. In addition, the wide range of security features in At Ease means that you can specify each user's access to information on the computer and prevent or allow different levels of information control. Finally, At Ease offers every user the privacy of his or her personal work space.

The person who controls users' access is the At Ease *owner*. In a home setting, the owner might be a parent; in a classroom or business setting, the owner might be a teacher or office manager.

The At Ease owner can decide which application programs and documents each user should have access to, where a user can open or save documents, and which menu commands and Apple menu items are available to a user.

For young or novice Macintosh users, the best working environment is the At Ease panels—a simple, easy-to-use interface where documents and programs are easily accessible. Like an application program, the At Ease panels run on top of the Finder (the Macintosh desktop), but the user doesn't see the Finder. The owner controls access to documents and programs, and can set security features restricting a user's ability to save, delete, and copy items.

For older or more experienced Macintosh users, the restricted Finder may be the best working environment. Its interface is very similar to the usual Macintosh desktop, but it lets the owner control access and set security features.

Users who need complete, unrestricted access to everything on the computer can use the regular Finder as their working environment.

You'll learn more about the working environments that At Ease supports when you register users in Chapter 3 of this manual.

About this book

This book is for the At Ease owner. Here's what you'll find in the remaining chapters:

- Chapter 2 provides instructions for installing the At Ease 3.0 software on your computer. (If you received At Ease with a Macintosh Performa computer, the software has been installed for you, and you can skip Chapter 2.)
- Chapter 3 describes how to use the At Ease Setup program to set up At Ease for your users.
- Chapter 4 discusses additional features of the At Ease Setup program.
- Chapter 5 provides tips and troubleshooting suggestions for getting the most out of At Ease.
- Appendix A explains how to use the At Ease panels in your daily work. You should share the information in this appendix with everyone who uses the At Ease panels as his or her working environment.
- Appendix B outlines the special features of the restricted Finder. You should share the information in this appendix with everyone who uses the restricted Finder as his or her working environment.

What you need to know before you begin

This book assumes that you have basic Macintosh skills. You should know how to

- use the mouse and keyboard
- choose commands from menus
- open folders and application programs
- save documents

If you need to learn more about these basic tasks, consult the learning materials that came with your computer.

Other sources of information


In addition to this book, you can take advantage of the on-screen instruction built into At Ease—Balloon Help and (if you are using system software version 7.5 or later) Apple Guide instructions for both At Ease Setup and At Ease itself.

When Balloon Help for At Ease is turned on, users of the At Ease panels can get information about any item on the screen simply by pointing to the item with the mouse. See “Using Balloon Help” in the “Getting Help” section of Appendix A.

With At Ease Setup Guide—available in the Guide (🔍) menu whenever At Ease Setup is the active program—you can get step-by-step instructions for using the At Ease Setup program. See “Getting On-Screen Instructions for At Ease Setup” in Chapter 3.

With At Ease Guide—available in the Guide (🔍) menu whenever At Ease is the active program—users can get step-by-step instructions for using the At Ease panels. See “Using At Ease Guide” in the “Getting Help” section of Appendix A.

You should check to see if there is any late-breaking news about At Ease that is not included in this book. If you have the *At Ease Install* disk, open the At Ease 3.0 Read Me file to find additional information. If you don't have this disk, open the At Ease 3.0 Read Me file on your hard disk. This file also includes information on the new features of version 3.0 of At Ease.



2

Installing At Ease on Your Computer



Before you can set up At Ease and begin using it, you need to install the software.

IMPORTANT If you received At Ease packaged with a Macintosh Performa computer, you can skip this chapter. (The At Ease software is already installed on your computer.) Continue with Chapter 3.

Restrictions on copying At Ease

As a licensed user of At Ease, you may use the software on a single Macintosh computer and make one copy for backup purposes. However, you are not permitted to distribute additional copies of the software. (For more details, see the software license agreement that came with At Ease.)

What do you need to run At Ease?

Your computer must have the following features to run At Ease 3.0:


- at least 4 megabytes (MB) of random-access memory (RAM) (5 MB if you want to use the Mouse Practice program)
- system software version 7.0 or later
- an internal or external hard disk
- a high-density (1.4 MB) floppy disk drive for the installation process

Installing At Ease

To install At Ease on your hard disk, you use the Installer program on the *At Ease Install* disk included in the At Ease package.

Make sure you have the *At Ease Install* disk ready.


- 1 Turn on your Macintosh and wait until the Macintosh desktop appears.
- 2 Insert the *At Ease Install* disk.



You should now see a window that looks like this:



- 3 Double-click the Installer icon.



A screen appears, welcoming you to the At Ease Installer.

4 Click the Continue button.

After a few moments, the Installer shows you this screen:




Make sure that the disk named is your startup disk (the disk with system software on it that you use to start up your computer; the startup disk's icon should be in the upper-right corner of your screen). If not, click Switch Disk until you see the name of your startup disk.

If you have limited hard disk space, you may need to use the Custom Install option. Choose Custom Install from the pop-up menu and select only those items you wish to install from the list that appears. (The only item you must select is At Ease Software.) To see information about a particular item, click the box marked with the letter *i* to the right of the item.

5 Click the Install button.

If any application programs are running, the Installer prompts you to quit those programs.

A status screen shows you the progress of the installation. When the installation is complete, you see this message:



6 Click Restart to exit from the Installer program and restart the computer.

Installing Mouse Practice

If you purchased At Ease as a software package, you also received a program called Mouse Practice. This program provides easy, step-by-step instructions for using the mouse. If any first-time users will be using your computer, you may want to install Mouse Practice.


If you received At Ease with a Macintosh Performa computer, you did not receive the Mouse Practice program. First-time users can learn mouse skills from the Performa Tutorial, available in the Launcher. (To use the Performa Tutorial, users must be in the Finder.)

WARNING Before a user opens the Mouse Practice program, make sure virtual memory is turned off in the Memory control panel.


To install the Mouse Practice program, follow these steps:

- 1 **Insert the *Mouse Practice Install* disk.**

You should now see a window that looks like this:



2 Double-click the Installer icon.



After a few moments, the Installer shows you this screen:




Make sure that the disk named is your startup disk (the disk with system software on it that you use to start up your computer; the startup disk's icon should be in the upper-right corner of your screen). If not, click Switch Disk until you see the name of your startup disk.

3 Click the Install button.

A status screen shows you the progress of the installation. When the process is complete, you see a message confirming that installation was successful.

4 Click Quit to leave the Installer program.

You're now ready to set up At Ease exactly as you want it. Turn to Chapter 3 for instructions.



3

Setting Up At Ease for Users

.....

This chapter describes the basic procedures to set up At Ease for your computer's users:


- opening the At Ease Setup program
- setting an administrator password
- registering yourself as the At Ease owner
- registering other users
- duplicating the privileges of an existing user
- removing users
- making changes to a user's access privileges
- turning At Ease on

Opening the At Ease Setup program

You use the At Ease Setup program to prepare your computer for use with At Ease. Follow these steps to open the program:

- 1 **Double-click the At Ease Setup Folder icon in the hard disk window to open the folder.**

Your window may not look exactly the same as the one shown here.



- 2 **Double-click the At Ease Setup icon to start the program.**




At Ease Setup

A Welcome screen appears.

- 3 **Click the OK button.**

The At Ease Setup window appears.




Getting on-screen instructions for At Ease Setup

If you prefer, you can use on-screen instructions instead of—or in addition to—the instructions in the rest of this chapter. The instructions available depend on which version of system software you are using.

On-screen instructions with system software version 7.0 or 7.1


If you are using system software version 7.0 or 7.1, the following button and text appear on each panel in the At Ease Setup program.



To get on-screen instructions, follow these steps:

- 1 **Click the button with the question mark icon.**

An At Ease Setup Help window appears.




- 2 **Read the information in the Help window.**
- 3 **If there is a button labeled Next, click it to see an additional Help panel.**


To return to a panel you've already seen, click the button labeled Previous.


- 4 **When you have finished reviewing the information in the Help window, click Done.**

On-screen instructions with system software version 7.5 or later


If you are using system software version 7.5 or later, step-by-step on-screen instructions for using the At Ease Setup program are available through a feature called Apple Guide. The following text appears on the opening screen of the the At Ease Setup program:



- 1 Pull down the Guide menu (marked with the  icon near the right end of the menu bar) and choose At Ease Setup Guide.



The At Ease Setup Guide access window appears.



Whenever you use At Ease Setup Guide, its window—either this access window or a panel displaying instructions—remains in front of other windows. If the window gets in your way, you can move it by dragging its title bar (the gray bar across the top of the window). Instruction panels also have a zoom box in the upper-right corner that lets you quickly reduce the size of the panel.

- 2 Notice the three buttons at the top of the window: Topics, Index, and Look For.



At Ease Setup Guide gives you three ways of finding information:

- **Topics** lets you choose from a list of general subjects; it is like the table of contents in a book.
- **Index** lets you choose from an alphabetical list of more specific subjects; it is like the index in a book.
- **Look For** lets you search for information related to a specific word or phrase that you type.

Getting information with the Topics button

If you prefer to find information by topic, follow these steps:

- 1 In the At Ease Setup Guide access window, click the Topics button.

A list of general topics appears on the left side of the window.

- 2 Click the desired topic area in the list of topics.

When you click any topic area, a list of related questions appears on the right side of the At Ease Setup Guide access window.

- 3 Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 4 When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Setup Guide access window. Or, if you are finished using At Ease Setup Guide, click the close box in the upper-left corner to close At Ease Setup Guide.

Getting information with the Index button

If you prefer to find information by index term, follow these steps:

- 1 In the At Ease Setup Guide access window, click the Index button.**

An alphabetical list of subjects appears on the left side of the window.

- 2 If necessary, scroll through the alphabetical list until the desired subject appears.**

You can scroll through the list either by dragging the slider to the desired letter or by using the scroll bar at the right of the list.

- 3 Click the desired subject in the alphabetical list.**

When you click any index entry, a list of related questions appears on the right side of the At Ease Setup Guide access window.

- 4 Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)**

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 5 When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Setup Guide access window. Or, if you are finished using At Ease Setup Guide, click the close box in the upper-left corner to close At Ease Setup Guide.**

Getting information with the Look For button

If you prefer to find information by searching for a specific word or phrase, follow these steps:

- 1 In the At Ease Setup Guide access window, click the Look For button.**

A small box appears on the left side of the window, where you can type text.

- 2 Click the arrow button to the left of the text box (or click inside the text box) to activate the box.**

- 3 **Type the desired word or phrase in the text box and then click Search.**

When you click Search, a list of questions related to the word or phrase you typed appears on the right side of the At Ease Setup Guide access window.

If At Ease Setup Guide is unable to locate any information on the word or phrase you typed, you'll see a message to that effect on the right side of the access window. Try typing a different word or phrase.

- 4 **Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)**

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 5 **When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Setup Guide access window. Or, if you are finished using At Ease Setup Guide, click the close box in the upper-left corner to close At Ease Setup Guide.**

Setting an administrator password

To prevent other users from changing access privileges, the At Ease owner needs to set an administrator password. Only users who know this password will be able to change access privileges in the At Ease Setup program.

IMPORTANT If you do not set an administrator password, every user will have access to the At Ease Setup program and can change access privileges for any user (including the owner).

- 1 **Choose Change Password from the Options menu.**



The Change Password screen appears.

Change Password

Enter your new password information:

Enter old password:

Enter new password:

Reenter new password:

Clue (optional):

Cancel OK

Type the password here.

Retype the password here to confirm.

Type a clue here to help you remember the password.

2 Type an administrator password in the box labeled “Enter new password.”

You can type up to 31 characters. As you type, dots (•••) appear in place of the text so that anyone nearby will be unable to see what password you have typed. Be sure to choose a password that only you would know.

3 Retype the administrator password in the box labeled “Reenter new password” to confirm it.

4 If you wish, click inside the box labeled “Clue” and type a clue that will help you remember your password.

The clue will appear each time you are asked to provide the administrator password. As with the password itself, be sure to choose a clue that only you will recognize.

5 Click OK.


In the future, you will need to provide the administrator password before you can use the At Ease Setup program. You can change the password at any time, by following the same steps as when you set the password—but only after entering the original password.

If you’ve forgotten the password, see “If You Forget the Administrator Password” in Chapter 5.


Registering yourself as the At Ease owner

Before you register other users, you should register yourself as the At Ease owner—that is, the person who controls other users' access on the computer. Follow these steps:

- 1 Click the **New** button in the **At Ease Setup** screen.



The **New User** screen appears.



- 2 Type your name in the upper box.
- 3 Click in the lower box and type a password for yourself.

Each time you start up the computer, you will be required to provide this password as part of the log-in process. (You can also use the administrator password to log in as yourself or any other user.)

4 Click the “switch to regular Finder” button.

Note that the Next button changes to a Done button.

5 Click the Done button.

You return to the At Ease Setup screen. Your name appears in the list of users.

Registering other users

Everyone else who will use your computer must be registered in the At Ease Setup program. At Ease allows you to register up to 40 users (including the owner) with different access privileges. Unless they know someone else’s password, unregistered users will not be able to proceed past the At Ease Welcome screen when starting up the computer.

The steps you follow to register a user depend on what working environment you want to assign the user:


- **At Ease panels** Users who start up with the At Ease panels see a simple, easy-to-use interface where programs and documents are easily accessible. As the At Ease owner, you can limit an At Ease user’s access to programs and documents, menu commands, locations for opening and saving, and more. At Ease is a particularly good working environment for novice or young Macintosh users. For a complete description of the At Ease panels interface, see Appendix A.
- **Restricted Finder** Users who start up with the restricted Finder see an interface that looks much like the traditional Finder (or Macintosh desktop). But unlike the regular Finder, the restricted Finder option lets the At Ease owner limit the user’s access in many of the same ways as the At Ease panels. The restricted Finder is a good working environment for more experienced Macintosh users whose access you want to control. For a description of the restricted Finder interface, see Appendix B.
- **Regular Finder** Users who start up with the regular Finder see the traditional Macintosh desktop. They have free access to all the documents and programs stored on the computer’s hard disk. The regular Finder is an appropriate working environment for yourself (as the At Ease owner) and any other users who should have unlimited access to the computer’s contents.

For each user, decide which working environment is appropriate and follow the complete sequence of steps in the corresponding section below.

Registering an At Ease user


To register a user who will start up with the At Ease panels, follow these steps:

- 1 Click the New button in the At Ease Setup screen.




Page 1 of the user setup pages appears. This is where you specify the user's name, password, and working environment.

- 2 Type the user's name in the upper box.



3 If you want to give this user a password, click in the lower box and type the password.

A password provides privacy for the user. Other At Ease users and restricted Finder users can't access documents that the user saves in his or her personal folder without providing the password. (As the At Ease owner, you—along with any other user who starts up with the regular Finder—have access to everything on the computer.) Passwords are generally unnecessary for young children, who probably don't need privacy on the computer and may not understand the concept of passwords.




If you assign a password for this user, he or she will be required to provide it each time he or she logs in. Be sure to make a note of the password so that you can inform the user of it.

Users can change their passwords whenever they like. But you can always log in as any user by providing the administrator password.


4 Click the Next button.

Page 2 of the user setup pages appears. This is where you specify the application programs and other items this user can have access to.



5 Click the Add Applications button.

At Ease searches your startup disk for all application programs. After a few moments, the Add Applications screen appears, listing all the programs that were found in the list on the left. (If you have a very large hard disk, it may take a while for the Add Applications screen to appear.)




Note: Apple II programs do not appear in this list. To add Apple II programs, you must use the Find Items command, explained in steps 11–16 of these instructions.

6 Select any programs that you want the user to have access to.

If you purchased At Ease as a software package, it came with a program called Mouse Practice. If the user hasn't had experience using the mouse, be sure to include Mouse Practice among the items you select.

To select more than one item in the list, hold down the Shift key while you click the names of the items.



7 Click Add.

The selected items move from the list on the left into the “Items for this User” list on the right.

As a shortcut, you can double-click programs or drag them from the list on the left to the list on the right.

8 If you want to give the user access to programs on another disk, use the Disk pop-up menu to view its contents. (If not, skip to step 10.)


To search a floppy disk other than the one currently in a floppy drive, select the current floppy disk in the Disk pop-up menu and click the Eject button. Then insert the floppy disk you want to search.

If you give the user access to programs on a CD-ROM disc or a floppy disk, the disk must be present in a drive in order for the user to open and use those programs. For programs on a CD-ROM disc, the disc must also be available to users in the CD-ROM Preferences screen. (See “Customizing Access to CD-ROM Discs” in Chapter 4 for more information.) For programs on a floppy disk, the user must also have access privileges to open and save on floppy disks, as described in steps 23 and 24 of this section.

9 Select the desired programs and click the Add button.


10 When you have finished adding programs, click OK.

You return to page 2 of the user setup pages. The programs you added now appear in the “Items for this User” list. (If you later decide to remove a program, select it in this list and click the Remove button.)



Click here to give the user access to other items, such as documents, control panels, or Apple menu items.

- 11** If you want to give the user access to any other items—for example, documents, individual control panels, or Apple menu items such as the Calculator—click the Find Items button. (If not, skip to step 16.)



Note: You can also use the Find Items screen to give users access to shared disks or file servers. For instructions, see “Giving Users Access to Shared Disks” in Chapter 4.

- 12** Type part or all of the item name in the upper box.

Typing part of the name can be a useful shortcut. However, if you type too short a selection, you may find more items than you want. For example, typing “car” would find all of the following items: “car,” “carnation,” “car repairs,” “day care,” and “scarf.”

- 13** If necessary, use the Disk pop-up menu to indicate which disk you want to search.

To search a floppy disk other than the one currently in a floppy drive, select the current floppy disk in the Disk pop-up menu and click the Eject button. Then insert the floppy disk you want to search.

If you give the user access to items on a CD-ROM disc or a floppy disk, the disk must be present in a drive in order for the user to open and use those items. For items on a CD-ROM disc, the disc must also be available to users in the CD-ROM Preferences screen. (See “Customizing Access to CD-ROM Discs” in Chapter 4 for more information.) For programs on a floppy disk, the user must also have access privileges to open and save on floppy disks, as described in steps 23 and 24 of this section.

14 Click the Find button.

A list appears on the left, showing all items on the selected disk whose names contain the text you typed.

15 Select the desired items and click the Add button.

To select more than one item in the list, hold down the Shift key while you click the names of the items.


As a shortcut, you can double-click items or drag them from the list on the left to the list on the right.

16 When you have finished adding items, click OK.

You return to page 2 of the user setup pages. The items you added now appear in the “Items for this User” list. (If you later decide to remove an item, select it in this list and click the Remove button.)

17 Click the Next button.

Page 3 of the user setup pages appears. This is where you can specify which menu commands the user will see. (For more information about the commands available in the At Ease menus, see “At Ease Menus” in Appendix A.)



- 18** If you want to limit user access to basic menu commands, click the Minimal button to select it.

This option restricts the user to such basic menu commands as Close, Quit, Restart, and Shut Down. The user cannot rename or delete files, create new folders, or access the Chooser or the Control Panels folder in the Apple menu.

- 19** If you want to give the user somewhat more access to menu commands, leave the Restricted button selected.

This option adds access to the Get Info command, the Find command, and the Chooser desk accessory to the Minimal menu command set, but the user still does not have access to commands for renaming or deleting files or creating new folders.

- 20** If you want to give the user access to the most possible menu commands, click the All button.

This option allows the user to perform a wider variety of file-management tasks, including renaming and deleting his or her own files, creating new folders, and changing the view of items on the At Ease screen.


Certain menu commands may be unavailable even when the All menu option is selected. For example, users who don't have access privileges to open and save items on floppy disks won't see the Copy To Floppy and Copy From Floppy commands.

- 21** If you want to activate the spoken button names feature of At Ease, click the checkbox labeled “Speak button names.”

At Ease gives you the option of having the computer speak the name of each button as the pointer passes over it on the screen. (This feature can be useful for children who have not yet learned to read or for people with visual disabilities.)

If you have attached a sound to an At Ease button (as described in “Adding and Removing Button Sounds” in Chapter 4), the computer will play the sound instead of speaking the name of the button.

IMPORTANT Before you use the spoken button names feature, you should turn off virtual memory in the Memory control panel.




22 Click the Next button.

Page 4 of the user setup pages appears. This is where you can set security features for this user.

Click this button to let the user open and save files in any folder on any disk.

Leave this button selected to limit the user to one, both, or neither of the save locations shown.



23 If you want the user to be able to open and save files in any folder on any disk, click the Anywhere button. Then skip to step 25.

This option gives the user the greatest freedom of file management, but it limits the owner's control over the arrangement of items on the computer's disks and also limits the privacy of other users.


When a user with this option chooses Save or Save As in a program, the dialog box that appears suggests the user's folder as the save location—but the user can use the dialog box to choose any location.

24 If you want to limit where the user can open and save items, leave the Only button selected, then use the checkboxes to specify a location or locations.

- To allow the user to open and save both in the user's folder and on floppy disks, make sure both checkboxes are selected.
- To allow the user to open and save only on a floppy disk, select the “on a floppy disk” checkbox and deselect the “in the user's folder” checkbox.
- To allow the user to open and save only in the user's folder, deselect the “on a floppy disk” checkbox and select the “in the user's folder” checkbox.
- To prevent the user from opening or saving anywhere, make sure neither checkbox is selected.

- 25** If you want the user to be able to make screen captures, click the “Allow the user to make screen captures” checkbox to select it; if not, leave it deselected.


Macintosh system software includes a screen-capturing feature that lets you take a “snapshot” of what’s currently on the screen by holding down the Command (⌘) and Shift keys while you type the number 3. If the “Allow the user to make screen captures” checkbox is selected, this user will have access to this feature.



Note: Screen captures are automatically stored in the user’s folder. If this user does not have the privileges to open and save items in the user’s folder, the screen-capturing feature is not available and the checkbox will be dimmed.

- 26** If you want to give the user access to the regular Finder, click the “Allow the user unrestricted access to the Finder” checkbox; if not, leave it deselected.

To give users even more freedom of file management, you can allow them unrestricted access to the regular Finder (the Macintosh desktop). When you select this option for a user, he or she will have access to all the documents and programs stored on the computer's hard disks. For that reason, you should consider carefully which users (if any) should be given this option.



Activating this option is different from setting the regular Finder as the user's working environment. In this case, the user will start up with the At Ease panels but can switch to the regular Finder using a menu command in the Special menu. (A password is not required for the user to switch to the regular Finder.)

- 27** Click the Done button.


You are now finished registering this user. If you want to change this user's access privileges in the future, you can always return to At Ease Setup and make any needed changes. (See “Making Changes to a User's Access Privileges” later in this chapter for instructions.)

If you have additional users to register, return to “Registering Other Users” earlier in this chapter and follow the appropriate set of instructions for the next user.

Registering a restricted Finder user


To register a user who will start up with the restricted Finder, follow these steps:

- 1 Click the **New** button in the **At Ease Setup** screen.



Page 1 of the user setup pages appears. This is where you specify the user's name, password, and working environment.

- 2 Type the user's name in the upper box.



3 If you wish to give this user a password, click in the lower box and type the password.

A password provides privacy for the user. Other restricted Finder users and At Ease users can't access documents that the user saves in his or her personal folder without providing the password. (As the At Ease owner, you—along with any other user who starts up with the regular Finder—have access to everything on the computer.) Passwords are generally unnecessary for young children, who probably don't need privacy on the computer and may not understand the concept of passwords.

The screenshot shows the 'New User' dialog box. It has a title bar with a lock icon. The 'User Name' field is filled with 'Mary'. The 'Password' field is filled with 'guidebooks'. Below these fields, there are three radio button options under the heading 'After startup:'. The first option, 'use the At Ease panels', is selected. The second option is 'switch to restricted Finder' and the third is 'switch to regular Finder'. At the bottom of the dialog, there are three buttons: 'Cancel', 'Previous', and 'Next'. The 'Next' button is highlighted with a red border.

If you wish, type a password for the user here.


If you assign a password for this user, he or she will be required to provide it each time he or she logs in. Be sure to make a note of the password so that you can inform the user of it.

Users can change their passwords whenever they like. But you can always log in as any user by providing the administrator password.

4 Click the “switch to restricted Finder” button.


5 Click the Next button.

Page 2 of the user setup pages appears. This is where you specify the application programs and other items this user can have access to.



6 Click the Add Applications button.

At Ease searches your startup disk for all application programs. After a few moments, the Add Applications screen appears, listing all the programs that were found in the list on the left. (If you have a very large hard disk, it may take a while for the Add Applications screen to appear.)




Note: Apple II programs do not appear in this list. To add Apple II programs you must use the Find Items command, explained in steps 12–17 of these instructions.

7 Select any programs that you want the user to have access to.

If you purchased At Ease as a software package, it came with a program called Mouse Practice. If the user hasn't had experience using the mouse, be sure to include Mouse Practice among the items you select.

To select more than one item in the list, hold down the Shift key while you click the names of the items.



8 Click Add.

The selected items move from the list on the left into the “Items for this User” list on the right.

As a shortcut, you can double-click programs or drag them from the list on the left to the list on the right.

- 9** If you want to give the user access to programs on another disk, use the Disk pop-up menu to view its contents. (If not, skip to step 11.)


If you want to search a floppy disk other than the one currently in a floppy drive, select the current floppy disk in the Disk pop-up menu and click the Eject button. Then insert the floppy disk you want to search.

If you give the user access to programs on a CD-ROM disc or a floppy disk, the disk must be present in a drive in order for the user to open and use those programs. For programs on a CD-ROM disc, the disc must also be available to users in the CD-ROM Preferences screen. (See “Customizing Access to CD-ROM Discs” in Chapter 4 for more information.) For programs on a floppy disk, the user must also have access privileges to open and save on floppy disks, as described in steps 23 and 24 of this section.

- 10** Select the desired programs and click the Add button.


- 11** When you have finished adding programs, click OK.

You return to page 2 of the user setup pages. The programs you added now appear in the “Items for this User” list. (If you later decide to remove a program, select it in this list and click the Remove button.)



Click here to give the user access to other items, such as documents, control panels, or Apple menu items.

- 12** If you want to give the user access to any other items—for example, documents, individual control panels, or Apple menu items such as the Calculator—click the Find Items button. (If not, skip to step 17.)



Note: You can also use the Find Items screen to give users access to shared disks or file servers. For instructions, see “Giving Users Access to Shared Disks” in Chapter 4.

- 13** Type part or all of the item name in the upper box.

Typing part of the name can be a useful shortcut. However, if you type too short a selection, you may find more items than you want. For example, typing “car” would find all of the following items: “car,” “carnation,” “car repairs,” “day care,” and “scarf.”

- 14** If necessary, use the Disk pop-up menu to indicate which disk you want to search.

If you want to search a floppy disk other than the one currently in a floppy drive, select the current floppy disk in the Disk pop-up menu and click the Eject button. Then insert the floppy disk you want to search.

If you give the user access to items on a CD-ROM disc or a floppy disk, the disk must be present in a drive in order for the user to open and use those items. For items on a CD-ROM disc, the disc must also be available to users in the CD-ROM Preferences screen. (See “Customizing Access to CD-ROM Discs” in Chapter 4 for more information.) For programs on a floppy disk, the user must also have access privileges to open and save on floppy disks, as described in steps 23 and 24 of this section.

15 Click the Find button.

A list appears on the left, showing all items on the selected disk whose names contain the text you typed.

16 Select the desired items and click the Add button.

To select more than one item in the list, hold down the Shift key while you click the names of the items.

As a shortcut, you can double-click items or drag them from the list on the left to the list on the right.

17 When you have finished adding items, click OK.

You return to page 2 of the user setup pages. The items you added now appear in the “Items for this User” list. (If you later decide to remove an item, select it in this list and click the Remove button.)


18 Click the Next button.

Page 3 of the user setup pages appears. This is where you specify which Apple menu items the user will see. (You can select all, none, or any combination of options.)

When this checkbox is selected, the user has access to most control panels and can change the way the computer is customized.

When this checkbox is selected, the user has access to most Apple menu items other than the Chooser and control panels.

When this checkbox is selected, the user has access to the Chooser desk accessory and can select printers and other devices.



19 If you want the user to be able to use the Chooser to select printers and other devices, leave the Chooser checkbox selected; if not, click the checkbox to deselect it.

20 If you want the user to be able to open control panels and make changes to the way the computer is customized, click the Control Panels checkbox to select it; if not, leave the checkbox deselected.

Even if you don't select the Control Panels checkbox, you can give the user access to individual control panels using the Find Items dialog box, described in steps 12–17 of these instructions.


21 If you want the user to have access to all other Apple menu items, leave the Other Apple Menu Items checkbox selected; if not, click the checkbox to deselect it.

22 Click the Next button.

Page 4 of the user setup pages appears. This is where you can set security features for this user.

Click this button to let the user open and save files in any folder on any disk.

Leave this button selected to limit the user to one, both, or neither of the save locations shown.



23 If you want the user to be able to open and save files in any folder on any disk, click the Anywhere button. Then skip to step 25.


This option gives the user the greatest freedom of file management, but it limits the administrator's control over the arrangement of items on the computer's disks and also limits the privacy of other users.

24 If you want to limit where the user can open and save items, leave the **Only** button selected, then use the checkboxes to specify a location or locations:

- To allow the user to open and save both in the user's folder and on floppy disks, make sure both checkboxes are selected.
- To allow the user to open and save only on a floppy disk, select the "on a floppy disk" checkbox and deselect the "in the user's folder" checkbox.
- To allow the user to open and save only in the user's folder, deselect the "on a floppy disk" checkbox and select the "in the user's folder" checkbox.
- To prevent the user from opening or saving anywhere, make sure neither checkbox is selected.

25 If you want the user to be able to make screen captures, click the "Allow the user to make screen captures" checkbox to select it; if not, leave it deselected.

Macintosh system software includes a screen-capturing feature that lets you take a "snapshot" of what's currently on the screen by holding down the Command (⌘) and Shift keys while you type the number 3. If the "Allow the user to make screen captures" checkbox is selected, this user will have access to this feature.



Note: Screen captures are automatically stored in the user's folder. If this user does not have the privileges to open and save items in the user's folder, the screen-capturing feature is not available and the checkbox will be dimmed.

26 Click the Done button.


You are now finished registering this user. If you want to change this user's access privileges in the future, you can always return to At Ease Setup and make any needed changes. (See “Making Changes to a User's Access Privileges” later in this chapter for instructions.)

If you have additional users to register, return to “Registering Other Users” earlier in this chapter and follow the appropriate set of instructions for the next user.

Registering a regular Finder user

To register a user who will start up with the regular Finder, follow these steps:

1 Click the New button in the At Ease Setup screen.



Page 1 of the user setup pages appears. This is where you specify the user's name, password, and working environment.

2 Type the user's name in the upper box.

The 'New User' dialog box is shown. The 'User Name' field contains the text 'John'. The 'Password' field is empty. Below these fields, there are three radio buttons under the heading 'After startup:'. The first radio button, 'use the At Ease panels', is selected. The second radio button is 'switch to restricted Finder', and the third is 'switch to regular Finder'. At the bottom of the dialog, there are three buttons: 'Cancel', 'Previous', and 'Next'. The 'Next' button is highlighted with a red border. A callout line points from the text 'Type the user's name here.' to the 'User Name' field.

3 If you wish to give this user a password, click in the lower box and type the password.

It's a good idea to assign a password to each regular Finder user. If you don't, At Ease users and restricted Finder users can log in as a regular Finder user and have access to everything on the computer.

The 'New User' dialog box is shown. The 'User Name' field contains the text 'John'. The 'Password' field contains the text 'pianissimo'. Below these fields, there are three radio buttons under the heading 'After startup:'. The first radio button, 'use the At Ease panels', is selected. The second radio button is 'switch to restricted Finder', and the third is 'switch to regular Finder'. At the bottom of the dialog, there are three buttons: 'Cancel', 'Previous', and 'Next'. The 'Next' button is highlighted with a red border. A callout line points from the text 'If you wish, type a password for the user here.' to the 'Password' field.

If you assign a password for this user, he or she will be required to provide it each time he or she logs in. Be sure to make a note of the password so that you can inform the user of it.

Users can change their passwords whenever they like. But you can always log in as any user by providing the administrator password.

4 Click the “switch to regular Finder” button.

Note that the Next button changes to a Done button.

5 Click the Done button.


You are now finished registering this user. If you want to change this user’s access privileges in the future, you can always return to At Ease Setup and make any needed changes. (See “Making Changes to a User’s Access Privileges” later in this chapter for instructions.)

If you have additional users to register, return to “Registering Other Users” earlier in this chapter and follow the appropriate set of instructions for the next user.

Duplicating an existing user's privileges

If you want to register a new user with exactly the same access privileges as an existing user, you can take advantage of a shortcut in the At Ease Setup program. Follow these steps:

- 1 In the At Ease Setup screen, click the name of the user whose access privileges you want to duplicate for the new user.



- 2 Click the Duplicate button.

The Duplicate User screen appears.



- 3 Type the name of the new user and click OK.

You are now finished registering this user. He or she will have exactly the same access privileges (including the password) as the user you duplicated. If you wish, you can change the password and other access privileges. (See “Making Changes to a User’s Access Privileges” later in this chapter for instructions.)

Removing users

If you decide to remove one or more users, follow the steps in this section.

WARNING When you remove a user, At Ease Setup also removes the user's folder and everything in it. If you don't want to lose the contents of the user's folder, make a backup copy or move the contents to another location before following these steps.

- 1 Open the At Ease Setup program and type the administrator password.
- 2 Select the name of each user you want to remove.
- 3 Click the Remove button.

Removed users will no longer be able to proceed past the At Ease Welcome screen.

Making changes to a user's access privileges

If you decide that you want to change a user's access privileges, follow these steps:

- 1 Open the At Ease Setup program and type the administrator password.
- 2 Click the name of the user whose access privileges you want to change.
- 3 Click Open.
- 4 Follow the instructions in the appropriate section of this chapter to make whatever changes you wish to the user's access privileges.

The changes will be effect the next time any user logs in.

- 5 Repeat steps 2–4 for each user whose privileges you want to change.

Turning At Ease on

When you first install At Ease, it is turned off. (This is also the case for Macintosh Performa computers.) To turn At Ease on, do this:

- In the At Ease Setup screen, click the On button.



The next time you restart the computer, At Ease will be on and you will see the At Ease Welcome screen. (See “Starting Up With At Ease” in Appendix A for details.)

Quitting the At Ease Setup program

When you have registered all of your users and turned At Ease on, choose Quit from the File menu. You return to the Macintosh desktop.

Where to go from here

To learn about additional features you can control with the At Ease Setup program, turn to Chapter 4.

To learn how to use the At Ease panels, turn to Appendix A.

To learn how to use the restricted Finder, turn to Appendix B.



4

Additional Features of At Ease Setup



This chapter describes advanced features of At Ease Setup that let you further control users' access to items and customize the computer for users. You'll also find instructions for turning At Ease off and removing At Ease permanently.

Customizing access to CD-ROM discs

If you have a CD-ROM drive connected to your computer, you may want to customize users' access to CD-ROM discs. You can give users access to all available CD-ROM discs, or restrict access to selected discs (and even selected items on a disc).


You customize access to CD-ROM discs using the CD-ROM Preferences command, available in the Settings menu. Settings you make using this command apply to all At Ease and restricted Finder users. (To limit a particular user's access, you must use the Add Applications and Find Items screens during the registration process, as described in Chapter 3.)

Users who start up with the regular Finder will have access to all available CD-ROM discs, regardless of the settings you make here.

To customize access to CD-ROM discs, follow these steps:

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.


- 2 Choose CD-ROM Preferences from the Settings menu.



The CD-ROM Preferences screen appears.


Click this button if you want all users to have access to all available CD-ROM discs.

Click this button if you want to limit users' access to CD-ROM discs.



- 3 If you want all At Ease and restricted Finder users to have access to all available CD-ROM discs, make sure the button labeled "Allow access to all CD-ROMs" is selected. Then skip to step 10.
- 4 If you want to limit which CD-ROM discs users will have access to, click the button labeled "Only allow access to the specified CD-ROMs."
- 5 Click the Add button.

The Add New CD-ROM screen appears, listing all CD-ROM discs currently available in CD-ROM drives connected to the computer.




6 To give access to a CD-ROM disc, select the disc name and click OK.

If the disc you want is not currently available, you can select another disc in the list and click the Eject button to eject it. Then insert the desired disc in the CD-ROM drive.

When you select a disc and click OK, you return to the CD-ROM Preferences screen, and the disc you selected now appears in the list of available discs.

7 If you want to limit users' access to particular items on a CD-ROM disc, select the disc name and click Settings. Otherwise, skip to step 10.

A Settings screen for the selected disc appears.



8 Use the checkboxes to specify which items users will have access to. (Only items whose checkboxes are selected will be available to users.)

As a shortcut to select or deselect all items at once, use the Select All or Select None buttons.

9 Click the OK button in the Settings screen for the disc.

10 Click the OK button in the CD-ROM Preferences screen.


Giving all users access to an item at the same time

If there are items you want all At Ease and restricted Finder users to have access to, you can take advantage of a shortcut in At Ease Setup to add items to all users at once. Follow these steps:

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Choose Add Item To All Users from the Options menu.



The Add File screen appears.



- 3 In the list of items that appears, select the item you want to give all users access to.

If the item you want is located on another disk, make sure that Desktop is selected in the pop-up menu; then select the disk in the list of items and click Open.

If the item is located in a folder, select the folder and click Open.

- 4 Click the Add button.

A message appears confirming that the selected item was added to all users.

- 5 Click the OK button.


Revoking all users' access to an item at the same time

If some or all At Ease or restricted Finder users currently have access to an item and you want to revoke everyone's access, you can take advantage of a shortcut in At Ease Setup to remove items from all users at once. Follow these steps:

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Choose Remove Item From All Users from the Options menu.



The Remove File From Users screen appears, listing all items that at least one At Ease or restricted Finder user currently has access to.



- 3 In the list of items, select the item you want to revoke all users' access to.
- 4 Click the Remove button.

A message appears confirming that the selected item was removed from all users.

- 5 Click the OK button.

Giving users access to shared disks

The At Ease owner can give users access to file servers or shared disks by creating buttons for them. You must connect to the shared disk before you can create a button for it.


Once you have created the button, the user can access that disk. In most cases, the user must be registered on the disk and must enter his or her name and password after connecting. However, some shared disks allow guest access.

To create an At Ease button for a shared disk you are connected to, follow these steps:

- 1** If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2** Select the user to whom you want to give access, then click Open.
- 3** Click the Next button.
- 4** Click the Find Items button.


The Find Items screen appears.

- 5** Type all or part of the name of the shared disk in the upper box.



6 Click the Find button.

A list appears on the left, showing all items whose names contain the text you typed, including any shared disks to which you are connected.



7 Select the shared disk in the list on the left, then click the Add button.

To select more than one item in the list, hold down the Shift key while you click the name of each item.

As a shortcut, you can double-click items or drag them from the list on the left to the list on the right.

When you have clicked Add, the shared disk you selected appears in the list on the right.

8 When you have finished searching and adding items, click OK.

9 Click the Next button.

10 Click the Next button again.

11 Click the Done button.

A button for the shared disk will appear on the user's panel the next time the user logs into At Ease.

Setting application preferences


Some application programs use special files that come with the program. And certain programs need to launch other programs (usually utility programs) in order to work properly. Sometimes these files or programs may not be available to a user because of security restrictions you have set for the user.

For example, the Writing Center comes with a set of pictures in the Pictures Folder. To use these pictures, the Writing Center application program must have access to that folder. But if a user does not have access to that folder, he or she will not be able to see or use these pictures.


The Application Preferences command lets the At Ease owner set a program's preferences. For most programs, the default settings in the Application Preferences dialog box are appropriate. But if you find that a program isn't working properly with At Ease, you may need to change the application preferences for the program.

To change the application preferences, follow these steps:

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Choose Application Preferences from the Settings menu.




The Set Application Preferences screen appears.



- 3 In the list on the left, select the name of the program whose preferences you want to set.

The selected program's current application preference settings appears at the bottom of the window.



- 4 If you wish, click the checkboxes to change the settings.

The default setting for the “open location” and “save location” checkboxes is active (selected) for most programs. These settings allow the program to access the necessary preference files, even if they are stored in folders to which the user doesn't have access.

The default setting for the “Can be launched by other applications” checkbox is inactive (deselected) for most programs. When selected, this option allows this program to be “sub-launched” by other programs even when a user doesn't have access to this program.

- 5 Repeat steps 4 and 5 for any other programs whose preferences you want to set.
- 6 When you are finished setting application preferences, click OK.

Changing the user greeting

Whenever an At Ease user starts up the computer, a Welcome screen appears. (If there is only one At Ease user, the Welcome screen will look somewhat different from the one pictured here.)



The At Ease owner can change the greeting at the top of this screen.

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Choose Change User Greeting from the Options menu.



The Change User Greeting screen appears.



- 3 Type a new user greeting and click OK.

The next time a user starts up with At Ease, the new greeting will appear at the top of the Welcome screen.

Adding and removing button sounds

You can attach sounds to items that appear on any user's At Ease panels. The computer will play the attached sound whenever a user moves the pointer over the button. (This is true even when the spoken button names feature has been turned on.)

In order to attach a sound, you must either have a sound file or the appropriate hardware and software to record a sound of your own.

Preparing to attach a sound

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Choose Attach Sounds from the Settings menu.



The Attach Sounds screen appears.



This screen shows you the name of every item to which at least one At Ease or restricted Finder user has been given access.

If the speaker icon to the left of an item name has wavy lines beside it, a sound has already been added to the item. (You can remove the sound and add a different one if you like.)

- 3 Click the name of the item to which you want to add a sound.

Now you can either import a sound or record one of your own.


Importing a sound

You must have a sound file on one of your disks in order to import a sound. Before you import a sound, make sure an item is selected in the Attach Sounds screen. (See the previous section for instructions.)



1 Click the Import Sound button.

The Import Sound screen appears.




2 If necessary, use the pop-up menu to locate a sound file.

3 Click the name of the sound you want to import.

If you want to hear the sound before importing it, click the Play Sound button.

4 Click the Import button to add the sound.

Wavy lines appear beside the speaker icon, indicating that the item now has a sound attached to it. The item's button will now play the sound when a user points to it.



5 Click the Done button.

Recording a sound


You must have the appropriate hardware and software in order to record a sound. (See the documentation that came with your computer for more information.)

Before you record a sound, make sure an item is selected in the Attach Sounds screen. (See “Preparing to Attach a Sound” earlier in this chapter for instructions.)



- 1 Click the Record Sound button.

The following window appears, with controls for recording sounds.



- 2 When you are ready to record a sound, click Record.
- 3 When you have finished recording, click Stop.
- 4 To hear the sound before you save it, click Play.
- 5 Click Save to save the sound.

Wavy lines appear beside the speaker icon, indicating that the item now has a sound attached to it. The item's button will now play the sound when a user points to it.

Removing a sound

Before you remove a sound, make sure an item is selected in the Attach Sounds screen. (See “Preparing to Attach a Sound” earlier in this chapter for instructions.)


Click Remove Sound.

The wavy lines disappear from beside the speaker icon, indicating that the item no longer has a sound attached to it. If the spoken button names feature is activated for a particular user, the item’s button will now speak its name when that user points to it.

Turning off At Ease

If you decide that you don’t want to use At Ease on your computer, you can turn it off.

- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Click the Off button in the first screen.



The next time you restart your computer, it will start up with the Finder.

Removing At Ease permanently

If you don't want to use At Ease, it's easiest just to turn it off. You can, however, remove it permanently.

The procedure you follow to remove At Ease depends on whether you have the *At Ease Install* disk available.

If you have the *At Ease Install* disk


- 1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.
- 2 Click the Off button in the At Ease Setup screen.

WARNING Do not attempt to remove At Ease without turning it off first.

- 3 Quit the At Ease Setup program.
- 4 Insert the *At Ease Install* disk into the disk drive.

If you don't have this disk, see the instructions in the next section, "If You Don't Have the *At Ease Install* Disk."

- 5 Double-click the Installer icon.
- 6 Click the Continue button in the Welcome screen that appears.
- 7 Choose Custom Remove from the pop-up menu.



8 Select all available checkboxes.

Some checkboxes may be dimmed, indicating that the items are not installed on your computer's hard disk.

9 Click the Remove button.

A message appears to let you know that removal was successful.

10 Click the Restart button to restart the computer.

If you don't have the *At Ease Install* disk

1 If necessary, open the At Ease Setup program, type the administrator password, and click OK.

2 Click the Off button in the first screen.

WARNING Do not attempt to remove At Ease without turning it off first.

3 Quit the At Ease Setup program.

4 Drag the At Ease files to the Trash.

The files you need to remove are

- the At Ease Setup Folder (at the top level of your startup hard disk, unless you have moved it); this folder contains the At Ease Setup program and (if you are running System 7.5 or a later version of system software) the At Ease Setup Guide file
- the At Ease Items folder (in your System Folder)
- the At Ease file (also in your System Folder)
- the At Ease Guide file (also in your System Folder, if you are running System 7.5 or a later version of system software)
- the At Ease Startup extension (in the Extensions folder of your System Folder)
- the At Ease Setup Help file (in the Preferences folder of your System Folder, if you are running System 7.0 or 7.1)

5 Hold down the Option key while you choose Empty Trash from the Special menu.



5

Tips and Troubleshooting

.....

This chapter includes tips for using At Ease most effectively, as well as suggestions for what to try if you run into problems using At Ease Setup or At Ease. This chapter also includes several points you should know if you're using At Ease 3.0 with System 7.5.

If you're having a problem and can't find an answer here or elsewhere in this manual (or in At Ease Guide or At Ease Setup Guide, available in the Guide [?] menu if you're using System 7.5 or a later version), see the service and support information that came with your computer for information about contacting Apple for additional help.

General tips

- Do not move the Finder or the At Ease Items folder out of your System Folder. (At Ease may not work properly if the Finder is not present.)
- If you want to give a user access to Apple II programs, you must use the Find Items feature during the registration process. The Add Applications feature does not recognize Apple II programs.
- If an At Ease user saves a document in a folder other than his or her user folder, the document will not appear on the user's panel.
- When you're using the Copy To Floppy or Copy From Floppy command, clicking Stop does not interrupt copying of the file in progress, but stops copying after it has been completed. Any additional files you selected are not copied.
- Do not run an Installer for another program from within At Ease. Turn off At Ease, return to the Finder, and then run the Installer for the other program.
- If you have turned on the spoken button names feature for a user, make sure that virtual memory is turned off whenever that user is logged into At Ease.

Troubleshooting suggestions

When I use the Find Items feature during the registration process, At Ease Setup doesn't find an item that I know is on the disk.

The characters you typed may not exactly match those in the item's name. Make sure you have included any necessary spaces or punctuation marks when you type in the name. Also, the Find Items feature does not find aliases or any other items that can't be opened (such as an extension or the System file).

I can't place an alias for a folder of items in the Documents folder for an At Ease user.

For security reasons, At Ease does not allow aliases for folders, except for the shared folder.

When At Ease is running and I try to install another application program on my startup disk, the pointer freezes on the screen.

Either turn off file sharing in the Sharing Setup control panel or turn off At Ease in the At Ease Setup program. Then install the other program.

Documents for At Ease users no longer show up on their At Ease panels.

You may have moved the Documents folder to a new location. The Documents folder must be either at the main level of the startup disk or on the desktop. If you've moved it, return it to one of these locations.

When I start up the computer, I see a message that At Ease has encountered an error.

Check to make sure your startup disk is not locked. (This is most likely to happen if you're using a removable cartridge drive for your startup disk.) Select the startup disk icon and choose Get Info from the File menu. If the Locked checkbox is selected, click it to remove the X.

If this does not solve the problem, the At Ease Setup information has probably been corrupted. If you have made a backup copy of your At Ease Items folder, you can try restoring it. Otherwise, you will need to reinstall At Ease, following these steps:

1. Restart the computer, holding down the Shift key.
2. If you have an administrator password, type the password and go to the Finder.
3. Throw away the At Ease Items folder and restart the computer.
4. Install At Ease and set it up again. (For complete installation instructions, see Chapter 2.)

Whenever I try to throw away the At Ease Items folder from the Finder and empty the Trash, I get a message that says some items are locked and could not be thrown away.

Some files in the At Ease Items folder are intentionally locked to prevent unauthorized deletion from within another program. If you want to delete the At Ease Items folder, drag it to the Trash and hold down the Option key while you choose Empty Trash from the Special menu.

If you forget the administrator password

If you've forgotten the administrator password, it's possible to set a new one.

IMPORTANT Following this procedure will also turn off At Ease, reset any application preferences you had changed, and reset the user greeting to “Welcome to At Ease” (if you had changed it). For instructions on changing the user greeting, see “Changing the User Greeting” in Chapter 4.

1 Start up your computer from another startup disk.

You'll need to start up from another disk that has system software on it. If your computer came with a disk called *Disk Tools*, you can use that disk.

2 Open the System Folder of your usual startup disk.

3 Open the At Ease Items folder inside your System Folder.

4 Drag the At Ease Preferences file into the Trash.

5 Hold down the Option key while you choose Empty Trash from the Special menu.

6 Restart from your usual startup disk.

7 Open the At Ease Setup program and set a new password.

For instructions, see “Setting an Administrator Password” in Chapter 3.

8 Before quitting the At Ease Setup program, turn on At Ease again.

For instructions, see “Turning On At Ease” in Chapter 3.

Tips for using At Ease 3.0 with System 7.5

At Ease 3.0 is compatible with System 7.5. However, some control panels and other features of System 7.5 may work differently while At Ease is running. This section provides information on these differences. Please refer to Macintosh Guide, available in the Guide (?) menu, for more information on these topics.

AppleScript

Scripts written using AppleScript can be launched by At Ease. However, scripts that require the Finder will not run properly.

Extensions Manager

You cannot change the settings in this control panel while At Ease 3.0 is running.

Find File

When At Ease 3.0 is open, the Find File command does not let you open or print items that are found.

General Controls control panel

Documents

This option can control where the Documents folder is created on your computer. At Ease always tries to open or save a document in the user's folder, within the At Ease Documents folder, regardless of the settings in the Documents option.

If At Ease is running and you have not changed the Documents option, At Ease creates the Documents folder on the startup disk. If At Ease is not running and you select the Documents folder button, the Documents folder is created on the desktop.

Launcher

The Launcher does not work with At Ease 3.0. If At Ease is turned on, the Launcher will not open at startup even if an alias to it is present in the Startup Items folder.

Macintosh Easy Open (version 1.1 or later)

If a user attempts to open a document without the application program that created it and Macintosh Easy Open is active, a message appears asking the user if he or she wants to open the document with another program. (Only programs that were made available to the user in the At Ease Setup program will appear in the list of programs.)

PowerTalk

Apple recommends that PowerTalk and At Ease not be used together, as some of PowerTalk's features will not work correctly.

QuickDraw GX

At Ease now supports printing with QuickDraw GX. However, once you start a print job, you cannot quit At Ease or go to the Finder until printing is completed. If QuickDraw GX is installed, print jobs that are stopped cannot be restarted within At Ease. The user (or the owner, if the user doesn't have access to the Finder) must go to the Finder to restart a print job.

Printer menu

When a user has access to the Chooser and QuickDraw GX is active, a new menu called "Printer" appears in At Ease. This menu contains all desktop printers that have been created, with a checkmark beside the name of the currently selected printer. To select a different printer, simply choose its name from the Printer menu.

Printer Status command

To view the status of the currently selected printer, choose Printer Status from the Printer menu. Print jobs started by the computer appear in the Printer Status window. A pop-up menu allows you to view the status of other printers.

Apple menu options

Users who start up with the At Ease panels do not see the Recent Applications, Recent Documents, or Recent Servers folders in the Apple (🍏) menu.

Users who start up with the restricted Finder see all three Recent folders, but their Recent Documents folder is deleted each time they quit At Ease. For that reason, there are no items in the Recent Documents folder at the beginning of a work session: documents are added to the folder only as they're used during the current work session.

If an At Ease or restricted Finder user has been given access to control panels, you can also give him or her the option to see a submenu for the Control Panels folder in the Apple menu.



Appendix A

Working in At Ease

.....

This appendix provides information on the day-to-day use of the At Ease working environment. The tasks described in this chapter are useful for all At Ease users—not just the owner. You may want to photocopy this appendix and share it with those users who work in the At Ease environment.

Starting up with At Ease

When you start up your computer with At Ease, a Welcome screen appears. (If there is only one At Ease user, the Welcome screen will look somewhat different from the one pictured here.)



- 1 **Select your name in the list on the left and click the Start button.**


The Enter Password screen appears.



If the At Ease owner did not assign you a password, you will see the At Ease desktop immediately upon logging in—you won't see the Enter Password screen.


- 2 **Type your password and click OK.**

You see the At Ease panels. (Your panels may look somewhat different from the ones pictured here.)



A first look at At Ease

The At Ease desktop includes at least one panel—the At Ease Items panel, which displays a button for each application program or document that is available to you. You may also see a user panel (labeled with your name) that contains items that you have saved in your personal area, as well as panels for any floppy disks and CD-ROM discs in drives connected to the computer.



The menus and menu commands you see depend on the access privileges you have been given by the At Ease owner. For an explanation of the menu commands, see “At Ease Menus” later in this chapter.

Switching between At Ease panels

There are three ways to switch between At Ease panels to find the documents or programs you want to work with.

- Choose the panel you want from the Panels menu.



The currently active panel is indicated by a checkmark in the Panels menu.

- Click the tab of the panel you want.



To switch between At Ease panels, click the tab of the panel you want.


- Press the Tab key on the keyboard until the panel you want is the active panel.

“Paging” through At Ease panels

If an At Ease panel contains more programs and documents than can be displayed at one time, a new “page” is added to the panel. An upturned page corner with an arrow appears in one or both bottom corners of the panel to indicate that there are additional items. The page number also appears at the bottom of the panel.

There are several ways to move between pages in At Ease:

- To go to the previous page, click the arrow in the lower-left corner; or, press the Left Arrow (←) key on the keyboard.
- To go to the next page, click the arrow in the lower-right corner; or, press the Right Arrow (→) key on the keyboard.




- To go directly to a specific page, hold down the Command (⌘) key while you type the number of the page.

This method works only for pages 1 through 9.

- To go to the first page, hold down the Command (⌘) key while you press and release the Left Arrow (←) key on the keyboard.
- To go to the last page, hold down the Command (⌘) key while you press and release the Right Arrow (→) key on the keyboard.

Opening programs, documents, and folders

- To open a program, document, or folder in At Ease, click its button once.



When you open a program or document, the At Ease desktop disappears, and you see the window of the program or document that you've opened.

When you open a folder, a new panel representing the folder's contents appears as the active panel.

At Ease menus

This section describes each of the At Ease menu commands. (Many of these commands work differently from those in the Macintosh Finder menus.)

All At Ease users see the commands described in this section as “always available.” Whether you see commands described as “optional” depends on the access privileges you have been assigned by the At Ease owner.

The Apple menu

The items in the Apple (🍏) menu are described in the manuals or on-screen help that came with your computer. Please refer to those sources if you have questions about Apple menu items. Note, however, that At Ease does not display folders (except for the Control Panels folder) in the Apple menu.

The File menu

The commands you see in the File menu depend on the access privileges you have been assigned by the At Ease owner. The following illustration shows all possible File menu commands.

File	
New Folder...	⌘N
Open Other...	⌘O
Close	⌘W
Rename...	⌘R
Delete...	⌘D
Get Info...	⌘I
Find...	⌘F
Copy To Floppy...	
Copy From Floppy...	
Quit	⌘Q


New Folder (optional)

If you have access to the New Folder command, you can use it to create new folders on your user panel or the panel for a floppy disk. After a new folder is created, you can save new documents in the folder, but you can't move any documents into the new folder.

To create a new folder, follow these steps:

- 1 If necessary, choose the panel on which you want to create a new folder from the Panels menu.
- 2 Choose New Folder from the File menu.

The New Folder screen appears.



- 3 **Type a name for the folder in the text box, and then click New Folder.**

A button for the new folder appears on the active panel.


Open Other (optional)

If you have access to the Open Other command, you can use it to open any program or document on any disk (unless you are required to open documents from your documents folder).

To open an item, follow these steps:

- 1 **Choose Open Other from the File menu.**

The Open Other screen appears.



- 2 **If necessary, use the pop-up menu to move to a different level or a different disk.**
- 3 **Select the item you want, and then click Open.**

The Open Other screen disappears, and the window of the selected program or document appears.

Close (always available)

This command allows you to close any folder panel that is currently open. It does not close the main At Ease panels, however.


Rename (optional)

If you have access to the Rename command, you can use it to rename any document or folder on your user panel or a floppy disk panel. Items on other panels can't be renamed.

To rename an item, follow these steps:


- 1 If necessary, choose the panel that contains the item you want to rename from the Panels menu.
- 2 Choose Rename from the File menu.

The first Rename screen appears.



- 3 Select the item you want to rename, and then click Rename.

The second Rename screen appears.



- 4 Type a new name for the item in the text box, and then click Rename.

The second Rename screen disappears, and the item has been renamed.

Delete (optional)

If you have access to the Delete command, you can use it to delete any document or folder on your user panel or a floppy disk panel. Items on other panels can't be deleted.

Locked items can't be deleted. (For information on unlocking an item so that it can be deleted, see “Get Info,” the next section in this chapter.)

If you delete a folder, you will also delete its contents permanently.

To delete an item, follow these steps:

- 1 If necessary, choose the panel that contains the item to be deleted from the Panels menu.
- 2 If necessary, open folders until the item you want to delete is visible.
- 3 Choose Delete from the File menu.

The Delete screen appears.



- 4 Select the item or items you wish to delete.

To select more than one item, hold down the Shift key while you click each name.

- 5 Click Delete.

A message appears asking whether you really want to delete the selected item or items.

- 6 To permanently delete the item or items, click Delete again.

If you decide you don't want to delete the item or items, click Cancel.

Get Info (optional)


If you have access to the Get Info command, you can use it to get information about any item on any At Ease panel.

You can also use the Get Info command to lock and unlock documents and to make a document into a stationery pad—that is, a document that serves as a template for other documents. (When you open a stationery pad, you are actually creating a copy that can be changed; the original remains unchanged.) The locking and stationery pad features apply only to documents on your user panel or a floppy disk panel.

To use the Get Info command, follow these steps:


- 1 If necessary, choose the panel that contains the item you want information about from the Panels menu.
- 2 Choose Get Info from the File menu.

The Get Info screen appears.



- 3 Select the item you want information about, and then click Get Info.

An information box appears.



- 4 If you want to lock the item, click the Locked checkbox to select it. (You can unlock the item by clicking the checkbox again to deselect it.)

When a document is locked, you can open and copy its contents, but you can't change or delete the file.

Only documents on your user panel or a floppy disk panel can be locked and unlocked.

- 5 If you want to make the item a stationery pad, click the checkbox labeled "Stationery pad" to select it.

Only documents on your user panel or a floppy disk panel can be made into stationery pads.

- 6 When you're finished using the Get Info feature, click OK.

Find (optional)

If you have access to the Find command, you can use it to find items on any At Ease panel (or in any folder on an At Ease panel). To find an item, follow these steps:

- 1 Choose Find from the File menu.**

The Find screen appears.

- 2 Type the name (or part of the name) of the item you want to find in the text box.**


Typing part of the name can be a useful shortcut. However, if you type too short a selection, you may find more items than you want. For example, typing “car” would find all of the following items: “car,” “carnation,” “car repairs,” “day care,” and “scarf.”

- 3 Click Find.**

A list appears in the Items Found box, showing all items whose names contain the text you typed.

- 4 Select the name of the desired item.**

Information about the selected item appears in the Info box, and the Go To button becomes active.



- 5 Click Go To.**

The Find screen disappears, and At Ease takes you to the panel with the selected item. The item flashes to help you locate it.

Copy To Floppy (optional)


If you have access to the Copy To Floppy command, you can use it to copy items from your user panel onto a floppy disk.

To copy items to a floppy disk, follow these steps:

- 1 If necessary, choose your user panel from the Panels menu.
- 2 Choose Copy To Floppy from the File menu.

If there is no disk in the floppy disk drive, At Ease prompts you to insert one.

The Copy To Floppy screen appears.



- 3 Select the item or items you want to copy.

To select more than one item, hold down the Shift key while you click each name.

- 4 If you want to delete the item or items from your user panel after copying them to a floppy disk, click the "Delete originals after copying" checkbox to select it.
- 5 Click Copy.

A message appears on the screen, showing you the status of the copying process. When the message disappears, the process is complete.

Note: If you click the Cancel button after copying has begun, At Ease will finish copying the item in progress but will not copy any additional items.

Copy From Floppy (optional)


If you have access to the Copy From Floppy command, you can use it to copy items from a floppy disk to your user panel.

To copy items from a floppy disk, follow these steps:

- 1 If necessary, choose your user panel from the Panels menu.
- 2 Choose Copy From Floppy from the File menu.

If there is no disk in the floppy disk drive, At Ease prompts you to insert one.

The Copy From Floppy screen appears.



- 3 Select the item or items you want to copy.

To select more than one item, hold down the Shift key while you click each name.

- 4 If you want to delete the item or items from the floppy disk after copying them to your user panel, click the "Delete originals after copying" checkbox to select it.
- 5 Click Copy.

A message appears on the screen, showing you the status of the copying process. When the message disappears, the process is complete.

Note: If you click the Cancel button after copying has begun, At Ease will finish copying the item in progress but will not copy any additional items.

Quit (always available)

This command returns you to the At Ease Welcome screen. From there, you can shut down the computer, or another user can start up At Ease.

Any floppy disks in the computer's floppy disk drives are ejected when you choose Quit.

The Edit menu

All users see the same Edit menu commands.

Edit	
Undo	⌘Z
Cut	⌘H
Copy	⌘C
Paste	⌘V
Clear	
Select All	⌘A

The commands in the Edit menu of At Ease are available only if you have selected a command that asks you to enter text (such as Rename or Find). Otherwise, the commands are dimmed. The At Ease Edit commands work exactly the same way as those in a program's Edit menu.

The View menu (optional)

If you have access to the commands in the View menu, you can use them to change the way items on an At Ease panel are arranged.

View	
✓by Name	
by Size	
by Kind	
by Date	

A checkmark indicates the current method of arrangement.

To change your view, follow these steps:

- 1 If necessary, choose the panel whose arrangement you want to change from the Panels menu.

You cannot change the arrangement of a CD-ROM disc panel.

- 2 Choose a view from the View menu.

There are four possibilities:

- *By Name* arranges the items in alphabetical order. (This is the default view.)
- *By Size* arranges the items according to size, starting with the largest item. When the pointer moves over the name of an item, At Ease displays the size below the name.
- *By Kind* arranges the items in alphabetical order by category (application program, document, and so on); in addition, documents are organized in alphabetical order by the program in which they were created. When the pointer moves over the name of an item, At Ease displays its kind below the name.
- *By Date* arranges the items by the date they were last modified, starting with the most recently modified item. When the pointer moves over the name of an item, At Ease displays the date it was last modified below the name.

The Special menu

The commands you see in the Special menu depend on the access privileges you have.

Special	
Turn Sound Off	
Eject Disk...	⌘E
Go To At Ease Setup	
Go To Finder	
Restart	
Shut Down	

Turn Sound Off (always available)

At Ease can make sounds when you move from one page to another, when you click a button, and when the pointer passes over an item. This command lets you turn off these sounds.

When sound has been turned off, this menu command changes to “Turn Sound On.”

Eject Disk (always available)

This command lets you eject any ejectable disk (such as a floppy disk or a CD-ROM disc) as well as an AppleShare volume (shared disk). If more than one disk is present, you will see a list to choose from when you choose this command.

If only one disk is present, the command name changes to “Eject <Name of Your Disk>.” For example, if a disk named “XYZ” is in the floppy disk drive, the command name will read “Eject XYZ.”

Go To At Ease Setup (always available)

This command takes you to the At Ease Setup program. If the At Ease owner has set an administrator password, you will be required to provide this password before you can gain access to At Ease Setup. Changes you make in At Ease Setup will not take effect until you quit At Ease and return to the Welcome screen.

Go To Finder (optional)

This command is available if the At Ease owner has given you unrestricted access to the Finder. Choosing this command brings the Finder forward; At Ease still runs in the background. You can return to At Ease by choosing Go To At Ease from the File menu of the Finder, or by choosing At Ease from the Application menu.

Restart (always available)

This command restarts the computer. Any floppy disks are ejected in the process of restarting. When the computer restarts, you see the At Ease Welcome screen.

Shut Down (always available)

This command shuts down the computer after first prompting you to save any open documents. Floppy disks are ejected in the process of shutting down.

Saving documents

When you save a new document, your choice of locations is determined by a setting in the At Ease Setup program. Check with the At Ease owner to see which of the following settings applies to you:

- *Anywhere:* You are allowed to save your documents anywhere on any disk. When you choose the Save or Save As command, you are presented with a directory dialog box that lets you select the location of your choice. Only items saved in the folder labeled with your name will appear on your user panel.
- *Only in your user folder:* You can save documents only in your personal folder on the startup disk. When you choose the Save or Save As command, you are presented with a directory dialog box that lets you save directly into your folder. (If you have access to the New Folder command, you can create additional folders within your personal folder.) When you return to the At Ease desktop, your documents appear on your user panel.
- *Only on a floppy disk:* You must use floppy disks to save your documents. When you choose the Save or Save As command, you are prompted to insert a floppy disk (unless one is already in a floppy disk drive).
- *Only in your user folder or on a floppy disk:* You can save documents either in your personal folder on the startup disk or on floppy disks. When you choose the Save or Save As command, you are presented with a directory dialog box that lets you save either directly into your folder or onto a floppy disk.
- *Nowhere:* You cannot save documents anywhere. When you choose the Save or Save As command, you see a message reminding you that you do not have the access privileges to save documents.


For more information on saving documents, refer to the manuals or on-screen help that came with your computer.

Changing your password


You can change the password given to you by the At Ease owner, as part of the process of starting up with At Ease.

If you were not given a password by the At Ease owner, you cannot use this procedure.

- 1 When you start up the computer, click the **Change** button in the **Enter Password** screen.



The Change Password screen appears.



- 2 Type your current password in the upper box, then type your new password in the middle and lower boxes.

As you type, dots (•••) appear in place of the text so that anyone nearby will be unable to see what password you have typed.

- 3 Click **OK**.

Setting the number of colors for a program


At Ease lets you set the number of colors (also called the *monitor depth*) that an application program will display when you use it. If you don't set the number of colors for a program, the program will display the number of colors set in the Monitors control panel. (Only users with access to the Control Panels folder in the Apple menu can adjust the control panel.)

To set the number of colors, follow these steps:

- 1 **Hold down the Option key while you click the program's button.**

The Monitor Depth screen appears.

- 2 **Use the pop-up menu to select a number of colors or grays.**



If you select a number of colors that your monitor does not support, your setting will have no effect.

When you select a number of colors in the pop-up menu, an X automatically appears in the box labeled “Set the screen to.” (To cancel your selection later, simply click this box to remove the X.)


- 3 **Click OK.**

Getting help

As you're learning At Ease, you may want to take advantage of Balloon Help, which lets you get information about items on the screen simply by pointing to them with the mouse. If you are using system software version 7.5 or later, you can also take advantage of At Ease Guide, which provides background information and step-by-step instructions on the screen.

Using Balloon Help


- 1 Choose **Show Balloons** from the Help (H) menu (System 7.0 or 7.1) or the Guide (G) menu (System 7.5).



When you have turned on Balloon Help, the menu command name changes to “Hide Balloons.”

- 2 Point to an item on the screen.

A balloon appears with a description of the item.




- 3 When you no longer need Balloon Help, choose **Hide Balloons** from the Help menu.

Using At Ease Guide

- 1 Pull down the Guide menu (marked with the ? icon near the right end of the menu bar) and choose At Ease Guide.



The At Ease Guide access window appears.



Whenever you use At Ease Guide, its window—either this access window or a panel displaying instructions—remains in front of other windows. If the window gets in your way, you can move it by dragging its title bar (the gray bar across the top of the window). Instruction panels also have a zoom box in the upper-right corner that lets you quickly reduce the size of the panel.

- 2 Notice the three buttons at the top of the window: Topics, Index, and Look For.



At Ease Guide gives you three ways of finding information:

- **Topics** lets you choose from a list of general subjects; it is like the table of contents in a book.
- **Index** lets you choose from an alphabetical list of more specific subjects; it is like the index in a book.
- **Look For** lets you search for information related to a specific word or phrase that you type.

Getting information with the Topics button

If you prefer to find information by topic, follow these steps:

- 1 In the At Ease Guide access window, click the Topics button.**

A list of general topics appears on the left side of the window.

- 2 Click the desired topic area in the list of topics.**

When you click any topic area, a list of related questions appears on the right side of the At Ease Guide access window.

- 3 Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)**

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 4 When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Guide access window. Or, if you are finished using At Ease Guide, click the close box in the upper-left corner to close At Ease Guide.**

Getting information with the Index button

If you prefer to find information by index term, follow these steps:

- 1 In the At Ease Guide access window, click the Index button.**

An alphabetical list of subjects appears on the left side of the window.

- 2 If necessary, scroll through the alphabetical list until the desired subject appears.**

You can scroll through the list either by dragging the slider to the desired letter or by using the scroll bar at the right of the list.

- 3 Click the desired subject in the alphabetical list.**

When you click any index entry, a list of related questions appears on the right side of the At Ease Guide access window.

- 4 Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)**

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 5 When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Guide access window. Or, if you are finished using At Ease Guide, click the close box in the upper-left corner to close At Ease Guide.**

Getting information with the Look For button

If you prefer to find information by searching for a specific word or phrase, follow these steps:

- 1 In the At Ease Guide access window, click the Look For button.**

A small box appears on the left side of the window, where you can type text.

- 2 Click the arrow button to the left of the text box (or click inside the text box) to activate the box.**

- 3 Type the desired word or phrase in the text box and then click Search.**

When you click Search, a list of questions related to the word or phrase you typed appears on the right side of the At Ease Guide access window.

If At Ease Guide is unable to locate any information on the word or phrase you typed, you'll see a message to that effect on the right side of the access window. Try typing a different word or phrase.

- 4 Click the desired phrase or question in the list on the right, and then click OK. (Or double-click the phrase or question.)**

A small window appears with information or instructions. If the information requires more than one panel, the right arrow in the lower-right corner is active. You can click this arrow to move to the next panel of the instructions.

- 5 When you have finished reading the information or following the instructions on all the panels in the sequence, click the Topics button in the lower-left corner to return to the At Ease Guide access window. Or, if you are finished using At Ease Guide, click the close box in the upper-left corner to close At Ease Guide.**

Tips and shortcuts

This section describes a number of tips and shortcuts that can help you to use At Ease more efficiently.

Moving quickly to a particular item on a panel

At Ease allows you to move quickly to a particular item on another page of a panel.

To move quickly to an item, follow these steps:

- 1 If necessary, choose the name of the panel that contains the item from the Panels menu.
- 2 Type the first character or characters of the item's name.


At Ease takes you to the page of the panel where the item appears. The item flashes to help you locate it.

Moving quickly between folders

If you have opened several levels of folders, you can use the following shortcut to move quickly between them:

- 1 Position the pointer over the topmost folder's name and hold down the mouse button.

A pop-up menu appears, showing all the folders that contain the current folder.



- 2 Drag through the pop-up menu until the desired folder is highlighted, then release the mouse button.

At Ease takes you directly to the desired folder.

Shortcuts for closing folders

If you have opened one or more folders on your user panel, you can use the following shortcuts to close one or all of them:

- **To close only the topmost folder, click its close box.**

The close box is located on the folder's tab, to the left of the folder's name and icon.



- **To close all open folders, hold down the Option key while you click the close box of the topmost folder.**

Working with more than one application program

You can work with more than one application program at a time in At Ease. Follow these steps:

- 1 Open the first program you want to work with.**

Your document window appears.

- 2 Choose At Ease from the Application menu.**

The Application menu is the farthest to the right in the menu bar.



The At Ease panels reappear.

- 3 Open the second program.**

The second document window opens. You can switch from one open program to the other by clicking in the window of the program you want, or by choosing the desired program from the Application menu.

Appendix B

Working in the Restricted Finder

.....

This appendix provides instructions for starting up the computer for restricted Finder users and outlines the main differences between the regular Finder and the restricted Finder. You may want to photocopy this appendix and share it with restricted Finder users.

Starting up with the restricted Finder

When At Ease is turned on, every user sees the same Welcome screen upon starting up the computer. (If there is only one registered user, the Welcome screen will look somewhat different from the one pictured here.)



- 1 **Select your name in the list on the left and click the Start button.**

The Enter Password screen appears.




If the At Ease owner did not assign you a password, you will proceed to the restricted Finder without seeing the Enter Password screen.

- 2 **Type your password and click OK.**

At Ease takes a few moments to prepare the restricted Finder. Any unlocked items that were left on the desktop of the startup disk by a regular Finder user are placed in a folder called “Secured Items” during this process.


Messages appear to show the progress of the preparation. Then you see the following screen:



A window labeled “Items for <Your Name>” opens automatically. This window usually includes two folders:

- “Items for <Your Name>” contains all the programs and documents that the At Ease owner has given you access to.
- “<Your Name>” is your personal folder, where you can store your own documents, create your own folders, and so on. (If the At Ease owner has limited you to opening and saving items only on floppy disks, you won’t see this folder.)

When you open these two folders, the screen looks something like this:



You can move and resize these windows during this work session. They will close automatically when you restart the computer, and the next time you open the folders, they will have the standard sizes and positions shown here.

Note: Because the two folder windows have the same name (your user name), you may prefer to leave the windows in their default position. That way, you won’t be confused about which window is which.

Differences between the regular Finder and the restricted Finder

Users familiar with the regular Finder should note the following differences:

- You can open only those application programs that the At Ease owner has given you access to (the ones that appear in the “Items for <Your Name>” folder or in the Apple menu).
- You can open a document only if it was created with one of the application programs that the At Ease owner has given you access to, or if it can be opened by a program that the At Ease owner has given you access to. (For example, if you have access to the SimpleText program, you may be able to open documents created by certain other word-processing programs, even if you don’t have access to the creating program.)
- You can open most folders on the computer’s disks—but you can’t open the personal folders of other users or the Secured Items folder.
- You can throw away only those items in the folder labeled “<Your Name>.”
- You can’t move any items onto the desktop.
- You can rename only those items in the folder labeled “<Your Name>.”
- If you haven’t been given the access privileges to open and save items on floppy disks, the computer will automatically eject any floppy disk that you try to insert.
- When you drag an item from a floppy disk into the folder labeled “<Your Name>,” you create a copy of the item in your folder. Keep in mind, however, that you will not be able to open the item—even if it’s in your own folder—unless you have been given access to the application program that was used to create it.
- File sharing cannot be used when you are in the restricted Finder.



Index

• • • • •

A

- access privileges
 - changing 17–18, 32, 42, 44, 46
 - for floppy disks 25, 26, 37, 38, 106
 - to menu commands 80
 - setting 23–32, 35–42
- Add Applications screen 23–24, 35–36
- Add File screen 52
- Add New CD-ROM screen 50
- administrator password
 - forgotten 70
 - logging in with 22, 34
 - setting 17–18
- aliases for folders 68
- Apple Guide, on-screen setup
 - instructions 14
- Apple menu 80
- Apple menu items 73, 80
 - setting user access to 39–40
- AppleScript, launching scripts 71
- AppleShare volume. *See* shared disks
- Apple II programs, setting user access to 23, 35, 68
- application preferences feature 56–57
- application programs
 - installing 69
 - opening 80, 82, 106
 - removing user access 25, 37
 - running multiple 102
 - setting number of colors 95
 - setting preferences 56–57
 - setting user access to 23–25, 35–37
- arrow keys, paging through panels 79
- At Ease Guide 3, 96, 97–100
- At Ease Guide access window 97
- At Ease Install* disk 3, 6, 64–65
- At Ease Items folder
 - deleting 69
 - restoring setup information 69
- At Ease Items panel 77
- At Ease menu commands 80–93
 - access privileges 77, 80
 - setting user access to 27–28, 39–40
- At Ease menus 80–93
- At Ease panels 2, 20
 - arranging items on 90–91
 - Balloon Help 3, 96
 - illustrated 76
 - paging through 79
 - reducing size 14
 - registering users 21–32
 - switching between 78

- At Ease program 1–2, 68
 - installing 5–7
 - installing other programs from 68
 - quitting 90
 - reinstalling 69
 - removing permanently 64–65
 - restrictions on copying 5
 - setting up 11–47, 49–65
 - skills required 3
 - starting up with 75–76
 - system requirements 5
 - with System 7.5 software 71–73
 - tips and shortcuts 101–102
 - turning off 63
 - turning on 47
 - working environments 20
 - working in 75–102
- At Ease Setup Guide 3, 14–17
 - closing 15, 16, 17
- At Ease Setup Guide access window 14–17
- At Ease Setup information, restoring 69
- At Ease Setup program. *See also* setting up At Ease
 - accessing from the Special menu 92
 - advanced features 49–65
 - basic setup procedures 11–47
 - duplicating an existing user's privileges 45
 - on-screen instructions 13–17
 - opening 12
 - quitting 47
 - registering At Ease panels users 20–32
 - registering regular Finder users 42–44
 - registering restricted Finder users 33–42
 - removing users 46
 - turning on At Ease 47
- Attach Sounds screen 60–63

B

- Balloon Help 3, 96
- buttons
 - adding/removing sounds 59–63
 - attached sounds 29
 - for shared disks 54–55
- by Date command (View menu) 91
- by Kind command (View menu) 91
- by Name command (View menu) 91
- by Size command (View menu) 91

C

- CD-ROM discs
 - customizing access to 49–51
 - ejecting 92
 - panels for 77
 - setting user access to items on 25, 26, 37, 38
- CD-ROM Preferences command (Settings menu) 49
- CD-ROM Preferences screen 25, 26, 37, 38, 50
- Change Password screen 18, 94
- Change User Greeting screen 59
- Chooser desk accessory, setting user access to 39–40
- Close command (File menu) 82
- colors, setting number of 95
- commands. *See* menu commands; and names of specific commands
- control panels, setting user access to 39–40
- Control Panels folder 73, 80, 95
- Copy From Floppy command (File menu) 68, 89
- Copy To Floppy command (File menu) 68, 88
- custom installation 7

D

- Delete command (File menu) 84
- deleting documents and folders 84, 88
- desktop
 - At Ease 1–2
 - Macintosh 2
- Disk pop-up menu (Find Items screen) 26, 38
- disks. *See* CD-ROM discs, floppy disks
- documents
 - deleting 84
 - locking/unlocking 85–86
 - making into stationery pads 85–86
 - opening 80, 82, 106
 - renaming 83
 - saving 93
 - setting user access to 26, 38
 - storage location of 68, 93
- Documents folder 69, 71
- Documents option (General Controls control panel) 71
- Duplicate User screen 45

E

- Edit menu 90
- Eject Disk command (Special menu) 92
- Enter Password screen 76, 94, 104
- Extensions Manager, changing settings 71

F

- File menu 81–90
- files. *See also* documents
 - setting user opening/saving privileges 30, 40–41
- file servers. *See* shared disks

- file sharing
 - and installing application programs 69
 - and the restricted Finder 106
- Find command (File menu) 87
- Finder. *See also* restricted Finder
 - accessing from the Special menu 92
 - allowing user access to 32, 44
 - compared with the restricted Finder 106
 - registering users 42–44
- Find File command, opening/printing items 71
- Find Items feature 23, 68
- Find Items screen, setting user access to items 26–27, 38, 54–55
- Find screen 87
- floppy disks
 - access privileges 25, 26, 37, 38, 106
 - copying items to/from 88–89
 - ejecting 24, 92
 - panels for 77
 - saving documents to 93
 - setting user access to items on 25, 26, 37, 38
 - setting user opening/saving privileges 30, 40–41
- folder panels, closing 82
- folders
 - aliases for 68
 - closing 102
 - creating new 81–82
 - deleting 84
 - moving between 101
 - opening 80, 106
 - renaming 83
 - setting user opening/saving privileges 30, 40–41

G

General Controls control panel
 Documents option 71
 Launcher 71
Get Info command (File menu) 85–86
Go To At Ease Setup command (Special menu) 92
Go To Finder command (Special menu) 92
Guide menu 14

H

help. *See* At Ease Guide; At Ease Setup Guide; Balloon Help
Help window (At Ease Setup) 13

I, J, K

importing sounds 60–61
Import Sound screen 61
Index button (At Ease Setup Guide access window) 15, 16, 97, 98, 99
information control 1
Installer program 6–9
installing At Ease 5–9
 custom installation 7
 on a hard disk 6–7
installing Mouse Practice 8–9
items. *See also* application programs; documents; files; folders
 adding/removing sounds 59–63
 copying to/from floppy disks 88–89
 deleting after copying 88–89
 finding 87
 getting information about 85–86
 giving/revoking all users' access to 52–53
 moving quickly to 101
 setting user access to 23–32, 35–42
 setting user opening/saving privileges 30, 40–41

L

Launcher (General Controls control panel) 71
license agreement 5
locking documents 85–86
Look For button (At Ease Setup Guide access window) 15, 16–17, 97, 98, 100

M

Macintosh desktop 2
Macintosh Easy Open 72
memory requirements 5
menu commands 80–93
 access privileges 77, 80
 setting user access to 27–28, 39–40
menus 80–93
monitor depth, setting 95
Mouse Practice Install disk 8
Mouse Practice program
 installing 8–9
 setting user access to 24, 36

N

New Folder command (File menu) 81–82
New User screen 19–20
 assigning passwords 22, 33–34, 43

O

on-screen setup instructions 13–17
 with system software version 7.0 or 7.1 13
 with system software version 7.5 or later 14–17
Open Other command (File menu) 82
owner
 defined 1–2
 registering 19–20

P

- pages, of At Ease panels 79
- panels. *See* At Ease panels
- Panels menu 78
- password
 - administrator 17–18, 22, 34, 70
 - changing 22, 34, 43, 45, 94
 - entering 76, 104
 - owner 19
 - user 21–22, 33–34, 43
- PowerTalk 72
- Printer menu (QuickDraw GX) 72
- printers
 - selecting 72
 - viewing status of 73
- printing, with QuickDraw GX 72–73
- Print Status command (QuickDraw GX) 73
- privileges. *See* access privileges
- programs. *See* application programs

Q

- question mark icon 13, 14
- QuickDraw GX 72–73
 - Printer menu 72
 - Print Status command 73
- Quit command (File menu) 90

R

- RAM (random-access memory)
 - requirements 5
- Read Me file 3
- Recent Applications folder 73
- Recent Documents folder 73
- Recent Servers folder 73
- recording sounds 62
- registering
 - At Ease panels users 20–32
 - regular Finder users 42–44
 - restricted Finder users 33–42

- regular Finder. *See* Finder
- Remove File From Users screen 53
- Rename command (File menu) 83
- renaming documents and folders 83, 106
- Restart (Special menu) 92
- restricted Finder 2, 20, 103–106
 - compared with the regular Finder 106
 - registering users 33–42
 - starting up with 103–105

S

- saving documents 93
- screen captures, allowing users to make 31, 41
- scripts, AppleScript 71
- Secured Items folder 104, 106
- security features, setting 2, 30–32
- selecting multiple items 24, 27, 36, 39
- Set Application Preferences screen 57
- setting up At Ease 11–47
 - administrator password 17–18
 - advanced procedures 49–65
 - duplicating an existing user's privileges 45
 - on-screen instructions 13–17
 - registering At Ease panels users 20–32
 - registering owner 19–20
 - registering regular Finder users 42–44
 - registering restricted Finder users 33–42
 - removing users 46
- shared disks
 - creating buttons for 54–55
 - ejecting 92
 - setting user access to 26, 38, 54–55
- shared folder, aliases for 68
- Shift key, selecting multiple items 24, 27, 36, 39
- Shut Down command (Special menu) 93
- shutting down the computer 93
- “snapshots” (screen captures), allowing users to make 31, 41

- sounds
 - adding/removing button sounds 59–63
 - attached to buttons 29
 - importing 60–61
 - recording 62
 - removing 63
 - turning on/off 92
- speaker icon 60–63
- Special menu 91–93
- spoken names feature 68
 - activating 29
- startup disk 69
- stationery pads, creating from documents 85–86
- switching between panels 78
- system requirements 5

T

- Tab key, switching between panels 78
- text-to-speech feature. *See* spoken button names feature
- Topics button (At Ease Setup Guide access window) 15, 97, 98
- troubleshooting 67–75
- turning off At Ease 63
- turning on At Ease 47
- Turn Sound Off command (Special menu) 92

U

- unlocking documents 85–86
- user folder, saving documents to 93
- user greeting, changing 58–59
- user panels 77

- users
 - changing access privileges 32, 42, 44, 46
 - duplicating an existing user's privileges 45
 - password 21–22, 33–34, 43
 - registering (At Ease panels) 20–32
 - registering (regular Finder) 42–44
 - registering (restricted Finder) 33–42
 - removing 46
 - setting access to items 23–32, 35–42
 - setting security features for 30–32
 - working environments 20, 21, 33

V

- View menu 90–91
- virtual memory, and the spoken button names feature 29, 68

W, X, Y

- Welcome screen 58, 75–76, 103
- working environments 20
 - specifying for users 21

Z

- zoom box (At Ease panels) 14